

TCL Z80 ASSEMBLER PAGE 0001

CODE	STMT	SOURCE	STATEMENT
0001		PSECT	ABS
0003			
0004			;MITSL - MONITOR IN TUSCAN SYSTEM 1
0005			;BY BRENDAN OWEN
0006			;ON 23/3/80
0007			;LAST MODIFIED ON 3/6/80
0008			;COPYRIGHT 1980, TCL SOFTWARE PRODUCTS LTD.
0009			
0010			
0011		EQU	03H
0012		EQU	04H
0013		EQU	08H
0014		EQU	09H
0015		EQU	0AH
0016		EQU	0DH
0017		EQU	0CH
0018		EQU	13H
0019		EQU	1BH
0020		EQU	1CH
0021		EQU	20H
0022		EQU	7FH
0023			
0024		EQU	'E'
0025		EQU	'*'
0026			
0027		EQU	0C3H
0028		EQU	0FFH
0029			
0030		EQU	80
0031		EQU	8
0032		EQU	127
0033			
0034		EQU	0F800H
0035		EQU	MONORG/256
0036		EQU	0F7FDH
0037		EQU	08000H
0038		EQU	0F000H
0039		EQU	0D400H
0040		EQU	0D700H
0041			
0042			
0043			
0044		EQU	0H
0045		EQU	1H
0046		EQU	2H
0047		EQU	3H
0048		EQU	7H
0049		EQU	0H
0050		EQU	1H
0051		EQU	2H
0052		EQU	3H
0053		EQU	4H
0054			
0055			
0056			
0057			
0058			
0059			

;DECIMAL NUMBER FLAG
;MONITOR PROMPT

;JUMP INSTRUCTION
;BREAKPOINT INSTRUCTION

;LENGTH OF INPUT BUFFER;
;NUMBER OF BREAKPOINTS
;DEFAULT DISPLAY FUNC LENGTH

;MONITOR ADDRESS
;PAGE NUMBER
;EDITOR ADDRESS
;PASCAL ADDRESS
;TRACE ROUTINE
;MEMORY MAPPED VDU ROUTINE
;INITIALISATION ROUTINE

;RS232 DATA OUT
;TAPE DATA OUT
;ONBOARD VDU PORT
;CENTRONICS PRINTER PORT
;CENTRONICS STROBE (BIT 0)
;RS232 UART STATUS
;RS232 DATA INPUT
;TAPE UART STATUS
;TAPE DATA IN
;I/O DEFINITION (BITS 4-7)
;B7 B6 (LIST DEVICE)
;0 0 RS232 OUT
;0 1 VDU OUT
;1 0 CENTRONICS OUT
;B5 B4 (CONSOLE DEVICE)