#### **NAME**

pcsname – get or set the PCS real name

#### **SYNOPSIS**

```
pcsname [-u \ user] [-s \ name] [-R \ program-root] [-D[=< n>]] [-V]
```

#### DESCRIPTION

#### Introduction

The posname program is used by the Personal Communication Services (PCS) user to get or to set his personal real name. Two PCS real names are available for use. These are the regular real name, and the (so-called) "full" real name. The regular real name is generally the real name of the user with an abbreviated middle initial only and no postnominal letters. This type of real name is usually already established by the system administrator when the user account was set up. The full real name is an optional additional name that can have non-abbreviated parts or postnominal letters appended. By default the regular real name of a user is set by the system administrator, but that real name can be changed by the use of this program. By default (without any program options specified) the regular real name of the user is printed to standard-output.

## **Options**

The following options can be used to change the mode of operation.

-u username	Operate on an alternative user besides the default calling user. Proper privileges are required for setting the origanization of another user.
-s name	This option allows for setting of a real name (either regular or full depending on the $\bf -f$ option) for the user. The real name should be quoted if it contains either whitespace or other characters that would be interpreted by a SHELL.
-f	This option specified that the fullname should be operated on rather than the regular real name. Without this option, only the regular real name is operated upon.
-R program-root	This option allows for setting the program-root of the program. This is largely used for special debugging purposes.
-V	This option makes the program print the version of the program to standard-error

## **ENVIRONMENT VARIABLES**

The following environment variables may change the default behavior of the program.

## PCSNAME PROGRAMROOT

This environment variable is taken to contain the program root over any other such environment variable. The **-R** argument overides this environment variable.

and then causes the program to exit (no other functions are performed).

PCS This environment variable is normally taken to contain the program root. The -R argument overides this environment variable.

#### PROGRAMROOT

This environment variable is taken to contain the program root if not other suitable environment variable this this purpose are in the environment. The -R argument overides this environment variable.

## **EXAMPLES**

simply get the current PCS regular real name of the user: (F

pcsname

get the current PCS full real name of the user: C?

pcsname -f

get the PCS regular real name for another user:

```
pcsname -u johny
```

set the regular real name:

```
pcsname -s "Adam Smith"
```

set the full real name:

```
pcsname -f -s "Adam Smith"
```

## SEE ALSO

```
pcsorg(1), pcsprojinfo(1), bb(1), vmail(1), msgs(1)
```

# PATH TO

This program is currently located in /usr/add-on/pcs/bin or possibly where ever PCS programs are stored on your system. This is often at \${PCS}/bin on some systems.

### WARNINGS

Be careful to put at one space between all option key letters and the associated key letter parameter.

## ACKNOWLEDGEMENTS

All previous PCS contributors and administrators.

## **AUTHOR**

David A.D. Morano