


Task 11)

Launch an EC2 instance and configure the root volume so that it is not deleted when the EC2 instance is terminated. After terminating the instance, verify that the root volume still exists.

Step 1: Launch EC2 Instance

Go to EC2 → Launch Instance → Select Operating System.




Step 2: Configure Storage

Scroll down to the Storage section.

Here you will see the root volume. Uncheck the option:


Delete on termination

This ensures the root volume will not be deleted when the instance is terminated.




Step 3: Launch Instance

Review the configuration and click Launch Instance.



Step 4: Verify Root Volume



The screenshot shows the AWS Management Console 'Volumes' page. The left sidebar lists navigation options like Savings Plans, Reserved Instances, and Elastic Block Store. The main content area shows a table of volumes with one volume selected: 'vol-03a48db7be922b081'. Below the table, the details for this volume are displayed, including its size (8 GiB), type (gp3), and status (In-use). A status check indicates 'Insufficient data'.

Name	Volume ID	Type	Size	IOPS	Throughput	Snapshot ID	Source volume
vol-03a48db7be922b081	vol-03a48db7be922b081	gp3	8 GiB	3000	125	snap-022e195...	-

Volume ID: vol-03a48db7be922b081

Volume ID	Size	Type	Status check
vol-03a48db7be922b081	8 GiB	gp3	Insufficient data

AWS Compute Optimizer finding
Opt-in to AWS Compute Optimizer for recommendations. [Learn more](#)


Volume state
In-use

IOPS
3000

Throughput
125

Step 5: Terminate EC2 Instance

Go to: EC2 → Instances → Select Instance → Instance State → Terminate Instance



The screenshot shows the AWS Management Console 'Instances' page. The left sidebar lists navigation options like Instances, Launch Templates, and Elastic Block Store. The main content area shows a table of instances with one instance selected: 'i-0e16c490a26528ccf'. Below the table, the details for this instance are displayed, including its state (Terminated), type (t3.micro), and availability (ap-south-1a).

Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability
volume-not-te...	i-0e16c490a26528ccf	Terminated	t3.micro	Initializing	View alarms +	ap-south-1a

i-0e16c490a26528ccf (volume-not-terminate)

Instance summary	Public IPv4 address	Private IPv4 addresses
i-0e16c490a26528ccf	-	-

IPv6 address
-



Instance state
Shutting down

Public DNS
-

Step 6: Verify Volume After Termination

Go to: EC2 → Volumes → Search Root Volume ID

If the volume status is Available, it means the volume was not deleted.



Final Result :

The EC2 instance was launched with the Delete on Termination option disabled for the root volume. After terminating the instance, the root volume remained available, confirming that the volume was not deleted.