H3 Reference Director

Workflow 01 v2.0 - Model files

Every model file the workflow uses: its exact name, where to download it, and which folder it goes in.

How to use this list. Click a link to download the file. Save it with the name shown, in the folder shown. All folders are inside **ComfyUI/models/**. Create a folder if it does not exist. When you are done, run the installer BAT: its model check tells you which files are complete, missing or damaged.

Only the four files in section 1 are required. Everything else belongs to an optional feature. Download a feature's files only if you want to use that feature.

1. Required - the workflow does not run without these

File name (keep it exactly)	Size	Folder inside ComfyUI/models/	Download
Minimax-h3_Singularity_ref2va_Pruned_v1.3_int8.safetensors	about 21 GB	diffusion_models	Download WarmBloodAban / Minimax-h3_Singularity
qwen3vl_32b_minimax_h3_nvfp4_awq.safetensors	about 15 GB	text_encoders	Download Comfy-Org / MiniMax-H3
minimax_h3_video_vae_fp16.safetensors	about 5 GB	vae	Download Comfy-Org / MiniMax-H3
minimax_h3_audio_vae_fp32.safetensors	about 0.6 GB	vae	Download Comfy-Org / MiniMax-H3

The first file is the base model. Singularity v1.3 is the default of Workflow 01 v2. These four are the loaders of Group 01.

2. Speed Mode - turbo LoRAs

Needed only for the TURBO 8-step and TURBO 4-step choices on the Speed Mode node (Group 04).

File name (keep it exactly)	Size	Folder inside ComfyUI/models/	Download
minimax_h3_ref2v_turbo_8step_v1.0_768p_comfyui_bf16.safetensors	about 1.9 GB	loras	Download lightx2v / Minimax-h3-Turbo
minimax_h3_ref2v_turbo_4step_v0.1_comfyui_bf16.safetensors	about 1.9 GB	loras	Download Comfy-Org / MiniMax-H3

3. LoRA Stack - the four named LoRAs

Each one is needed only if you switch that LoRA on. If a file ends up with a different name on your disk, pick it in that LoRA's **..._file** field on the LoRA Stack node.

File name (keep it exactly)	Size	Folder inside ComfyUI/models/	Download
h3-realism-people-t2v-i2v-r2v.safetensors	about 125 MB	loras	Download fal / MiniMax-H3-Realism-People-LoRA
Motion_Repair_V2.safetensors	about 155 MB	loras	Download JOKER141 / MiniMax-H3-General-Motion-Continuity-Repair
wushu_spatial_physics_clean_3000_pruned.safetensors	about 155 MB	loras	Download Jojocodex / minimax-h3-spatial-physics-lora
minimax_h3_lms_v1.0_r64.safetensors	about 1.2 GB	loras	Download Alissonerdx / Minimax-H3-ComfyUI

4. Feature models

File name (keep it exactly)	Size	Folder inside ComfyUI/models/	Download	Used by
minimax_h3_latent_upscaler_3d_conv_v1_fp16.safetensors	about 0.7 GB	latent_upscale_models	Download LBH-123-AI / Minimax_h3_latent_Upscaler	Group 07, latent upscale
face_yolov8m.pt	about 50 MB	ultralytics/bbox	Download Bingsu / adetailer	Group 08, face refine
taeh3.safetensors	small	vae_approx	Open the Files page Kijai / MiniMax-H3-TAE	Group 04, live preview (on by default)

- **Upscaler file name.** The repository used to call this file minimax_h3_latent_upscaler_3d_fp16.safetensors. It is the same model. If your file has that older name, the model_name field on the node UPSCALE 2 shows red: click it and pick your file once.
- **Live preview is ON in the workflow.** It needs taeh3.safetensors. Without that file the render may not start: download it, or select the node LIVE PREVIEW in Group 04 and press Ctrl+B to switch the preview off.
- **Motion refine (Group 06)** needs no model file. It uses the ComfyUI-MAINodes node pack, which the installer adds.

5. Optional alternatives

Not needed. They are other choices for a dropdown that already has a default.

File name (keep it exactly)	Size	Folder inside ComfyUI/models/	Download	What it replaces
minimax_h3_ref2va_pruned_int8_convrot.safetensors	about 20 GB	diffusion_models	Download Comfy-Org / MiniMax-H3	Base model: the official Ref2VA (the Version 1 model)
MiniMax-H3-ref2va-pruned-zs05-comfy-int8.safetensors	about 21 GB	diffusion_models	Open the Files page Darkbluu / MiniMax-H3-x-Z-Image-Graft	Base model: H3 x Z-Image graft
minimax_h3_video_vae_int8_convrot.safetensors	about 3 GB	vae	Download Comfy-Org / MiniMax-H3	Video VAE: a faster int8 version

6. Downloading without problems

- **Let each download finish.** A browser shows a temporary name (.crdownload, .part) while a file is still arriving. Never rename a temporary file: it is incomplete and ComfyUI will report it as corrupt.
- **Check the size.** A finished file is close to the size in this list. A much smaller file was cut short.
- **Keep the names.** The workflow's dropdowns are set to these exact names. A LoRA with a different name can still be used: pick it in its ..._file field.
- **Press R in ComfyUI** after adding files while ComfyUI is open, so the dropdowns refresh.
- **Run the installer again.** Its model check compares every file with the size Hugging Face lists and checks that each .safetensors file is complete. It changes nothing; it only reports.

Folder map

Folder (inside ComfyUI/models/)	What goes in it
diffusion_models	The base model
text_encoders	The Qwen3-VL text encoder
vae	The video VAE and the audio VAE
loras	The two turbo LoRAs and the six LoRA Stack files (subfolders are fine)
latent_upscale_models	The latent upscaler model
ultralytics/bbox	The face detector
vae_approx	The live-preview decoder

Sizes are rounded. Where the table says 'Open the Files page', the file sits on that page: click the file name there, then the download arrow.