

IP Addressing Table

Unit	Hosts Needed	Prefix	Network Address	Subnet Mask	First Usable	Last Usable	Broadcast
Command Center HQ	2000	/21	1.2.0.0	255.255.248.0	1.2.0.1	1.2.7.254	1.2.7.255
Simulation Core	600	/22	1.2.8.0	255.255.252.0	1.2.8.1	1.2.11.254	1.2.11.255
Testing Sandbox	600	/22	1.2.12.0	255.255.252.0	1.2.12.1	1.2.15.254	1.2.15.255
ML Engine	425	/23	1.2.16.0	255.255.254.0	1.2.16.1	1.2.17.254	1.2.17.255
Data Processing Cell	425	/23	1.2.18.0	255.255.254.0	1.2.18.1	1.2.19.254	1.2.19.255
Diagnostics Bay	300	/23	1.2.20.0	255.255.254.0	1.2.20.1	1.2.21.254	1.2.21.255
Repair Unit	300	/23	1.2.22.0	255.255.254.0	1.2.22.1	1.2.23.254	1.2.23.255
Emergency Control Node	80	/25	1.2.24.0	255.255.255.128	1.2.24.1	1.2.24.126	1.2.24.127
HQ ↔ Emergency Node	2	/30	1.2.24.128	255.255.255.252	1.2.24.129	1.2.24.130	1.2.24.131
HQ ↔ Sim Core	2	/30	1.2.24.132	255.255.255.252	1.2.24.133	1.2.24.134	1.2.24.135
Sim Core ↔ AI Unit	2	/30	1.2.24.136	255.255.255.252	1.2.24.137	1.2.24.138	1.2.24.139
Sim Core ↔ Hangar	2	/30	1.2.24.140	255.255.255.252	1.2.24.141	1.2.24.142	1.2.24.143
Sim Sandbox ↔ AI Unit	2	/30	1.2.24.144	255.255.255.252	1.2.24.145	1.2.24.146	1.2.24.147
Sim Core ↔ Sim Sandbox	2	/30	1.2.24.148	255.255.255.252	1.2.24.149	1.2.24.150	1.2.24.151
Diag Bay ↔ Repair Unit	2	/30	1.2.24.152	255.255.255.252	1.2.24.153	1.2.24.154	1.2.24.155