



# z/OS Introduction and Workshop

TN3270, FTP, and SSH Access



# **Unit Objectives**

After completing this unit, you should be able to:

- Briefly describe 3270
- Access z/OS using TN3270 Emulator
- Access z/OS using SSH client (PuTTY)
- Access z/OS using FTP



## 3270 Protocol

3270 is an IBM display device introduced in 1971

- Text only display
- Session attributes determine screen number of rows and columns
- Existed long before HTML and Browsers
- VT100 (text display) introduced in 1978

3270 protocol is a 'data stream' consisting of commands and orders to:


- Write data to display device
- Read data from display device

3270 Emulator Keyboard Mapping vs. PC Keyboard Layout

- 3270 protocol 'enter' command, x'7D', is used to send screen data
- PC keyboard right side 'Ctrl' is mapped by emulator to generate 'enter' command
- Emulator keyboard mapping can be changed



# 3270 Emulator Mapping to Physical Keyboard



Right side Ctlr key generates 3270 'enter' command by default



## TN3270 Configuration Customization Options

IP address (target system)

Port number (target system application)

Model size (screen # rows and # columns)

Code page (1047 recommended)

**Keyboard Mapping** 



## TN3270 signon screen following successful configuration

```
### Z/OS V2 R2 via TCPIP Telnet ***
```

```
Choose from the following commands:
(Not all applications are available in every system.)

TSO - Logon TSO (24x80)

IMS - Logon IMS
CICS - Logon CICS TS 5.3
```



CICS42 - Logon CICS TS 4.2



## TN3270 signon screen following successful configuration

```
==WELCOME==TO THE===== =====
              IBM Innovation Center - Dallas== ===
MVR22GA
                  z/OS V2 R2 via TCPIP Telnet ***
Choose from the following commands:
(Not all applications are available in every system.)
TS0
       - Logon TS0 (24x80)
IMS
      - Logon IMS
CICS
      - Logon CICS TS 5.3
CICS42 - Logon CICS TS 4.2
    type tso – then 'enter' command – right side Ctrl key
```

```
IKJ56700A ENTER USERID - zibm050
```

type your assigned ID – then 'enter' command – right side Ctrl key

tso



## Tab to Password field enter bluesky, New Password required with verification

```
------ TSO/E LOGON ------
IKJ56447A Reenter the new password in the NEW PASSWORD field for verification
  Enter LOGON parameters below:
                                             RACF LOGON parameters:
  Userid ===> ZIBM050
  Password ===>
                                            *New Password ===>
  Procedure ===> DBPROCBG
                                             Group Ident ===>
  Acct Nmbr ===> FB3
  Size ===> 32768
  Perform ===>
  Command ===>
  Enter an 'S' before each option desired below:
                                 -Reconnect -OIDcard
         -Nomail
                       -Nonotice
PF1/PF13 ==> Help PF3/PF15 ==> Logoff PA1 ==> Attention PA2 ==> Reshow
You may request specific help information by entering a '?' in any entry field
```



## TSO logon writes message to display device

ICH70001I ZIBM000 LAST ACCESS AT 10:49:16 ON TUESDAY, APRIL 4, 2017 ZIBM000 LOGON IN PROGRESS AT 10:51:44 ON APRIL 4, 2017 NO BROADCAST MESSAGES

z/OS Introduction and Workshop

Today is 4 Apr 2017

Time in Central USA is 10:51:49

You logged on with ID ZIBM000

Have Fun!



## TSO logon writes message to display device

```
Enter to proceed to ISPF
Total allocation time - 14.606627
***
```

when \*\*\* is displayed, enter to proceed

10



## TSO automatically starts ISPF

```
Menu Utilities Compilers Options Status Help
                           ISPF Primary Option Menu
                                           More:
0 _Settings
                 Terminal and user parameters
                                                         User ID . : ZIBM050
  View
1
                 Display source data or listings
                                                         Time. . . : 14:01
  Edit
                 Create or change source data
                                                         Terminal.: 3278
  Utilities
                 Perform utility functions
                                                         Screen. . : 1
  Foreground
                 Interactive language processing
                                                         Language. : ENGLISH
4
  Batch
                 Submit job for language processing
                                                         Appl ID . : ISR
6
  Command
                 Enter TSO or Workstation commands
                                                         TSO logon : DBPROCBG
                Perform dialog testing
  Dialog Test
                                                         TSO prefix: ZIBM050
                 Library administrator functions
 LM Facility
                                                         System ID : SOW1
  IBM Products
                IBM program development products
                                                         MVS acct. : FB3
                                                         Release . : ISPF 7.2
10 SCLM
                 SW Configuration Library Manager
11 Workplace
                 ISPF Object/Action Workplace
                 ----- Other Install Products -----
D Debug Tool Debug Tool Utility V13.1
                                                                          change settings
SD SDSF
                 System Display and Search Facility
IP IPCS
                 Inter Problem Control Facility
IS ISMF
                 Inter Storage Management Facility
SM SMP/E
                 SMP/E and CBIPO Dialogs
HC HCD
                 HW Configuration Definition Dialog
R RACF
                 Resource Access Control Facility
S DFSORT
                 Data Facility Sort
OE OEDIT
                 OpenEdition MVS Edit files
OB OBROWSE
                 OpenEdition MVS Browse files
OS OSHELL
                 OpenEdition MVS ISPF Shell
BR READ
                 BookManager READ/MVS
BB BUILD
                 BookManager BUILD/MVS
BI READ INDEX
                 BookManager Index Utility
Licensed Materials - Property of IBM
              Copyright IBM Corp. 1980, 2015.
5650-Z0S
US Government Users Restricted Rights -
                                                ns
Use, duplication or disclosure restricted
by GSA ADP Schedule Contract with IBM Corp.
                                                B2
                                                n
Option ===> =0
                           F3=Exit
                                        F7=Backward
F1=Help
              F2=Split
                                                     F8=Forward
                                                                  F9=Swap
F10=Actions F12=Cancel
```

© 2017 IBM Corporation



## **ISPF Settings**

Terminal Characteristics

Screen format 2 1. Data

#### **Before**

Log/List Function keys Colors Environ Workstation Identifier Help

#### ISPF Settings

#### Options | Print Graphics Enter "/" to select option Family printer type 2 Command line at bottom Device name . . . . Panel display CUA mode Aspect ratio . . . 0 Long message in pop-up Tab to action bar choices Tab to point-and-shoot fields General Restore TEST/TRACE options Input field pad . . B Session Manager mode Command delimiter . : Jump from leader dots Edit PRINTDS Command Always show split line Enable EURO sign Member list options Enter "/" to select option Scroll member list Allow empty member list Allow empty member list (nomatch) Empty member list for edit only

| Terminal Type | 3 | 1. 3277    | 2. 3277A   | 3. 3278    | 4. 3278A   |
|---------------|---|------------|------------|------------|------------|
| •             |   | 5.3290A    | 6. 3278T   | 7. 3278CF  | 8. 3277KN  |
|               |   | 9. 3278KN  | 10. 3278AR | 11. 3278CY | 12. 3278HN |
|               |   | 13. 3278HO | 14. 3278IS | 15. 3278L2 | 16. BE163  |
|               |   | 17. BE190  | 18. 3278TH | 19. 3278CU | 20. DEU78  |
|               |   | 21. DEU78A | 22. DEU78T | 23. DEU90A | 24. SW116  |
|               |   | 25. SW131  | 26. SW500  | 27. 3278GR | 28. 3278L1 |

3. Max

4. Part

2. Std

29. OTHER

| Command ===> | 1          |         |             |            |         |  |
|--------------|------------|---------|-------------|------------|---------|--|
| F1=Help      | F2=Split   | F3=Exit | F7=Backward | F8=Forward | F9=Swap |  |
| F10=Actions  | F12=Cancel |         |             |            | •       |  |

### After

Log/List Function keys Colors Environ Workstation Identifier Help

#### ISPF Settings

```
Print Graphics
Options
  Enter "/" to select option
                                            Family printer type 2
     Command line at bottom
                                            Device name . . . .
     Panel display CUA mode
                                            Aspect ratio . . . 0
    Long message in pop-up
     Tab to action bar choices
     Tab to point-and-shoot fields
                                          General
     Restore TEST/TRACE options
                                            Input field pad . . B
     Session Manager mode
                                            Command delimiter . :
     Jump from leader dots
     Edit PRINTDS Command
     Always show split line
    Enable EURO sign
Member list options
  Enter "/" to select option
    Scroll member list
     Allow empty member list
    Allow empty member list (nomatch)
     Empty member list for edit only
Terminal Characteristics
                                                      4. Part
  Screen format
                 3 1. Data
                                2. Std
                                           3. Max
                       1. 3277
                                     2. 3277A
                                                    3. 3278
                                                                 4. 3278A
  Terminal Type
                       5. 3290A
                                     6. 3278T
                                                   7. 3278CF
                                                                 8. 3277KN
                       9. 3278KN
                                    10. 3278AR
                                                  11. 3278CY
                                                                 12. 3278HN
                      13. 3278H0
                                    14. 3278IS
                                                  15. 3278L2
                                                                 16. BE163
                      17. BE190
                                    18. 3278TH
                                                  19. 3278CU
                                                                 20. DEU78
  Return
                      21. DEU78A
                                    22. DEU78T
                                                  23. DEU90A
                                                                 24. SW116
                      25. SW131
                                    26. SW500
                                                  27. 3278GR
                                                                 28. 3278L1
    Exit
                      29. OTHER
     F3
Command ===>
F1=Help
                           F3=Exit
                                        F7=Backward F8=Forward F9=Swap
```


F2=Split

F10=Actions F12=Cancel




### Program Function key display off, 'x' to terminate ISPF session, then logoff of TSO






### After





## SSH connection



enter key is PC labeled enter key


use same TN3270 access assigned ID and your password

login as: zibm000 zibm000@192.86.32.159's password: ZIBM000:/u/zibm000: >exit

© 2017 IBM Corporation



## FTP connection



© 2017 IBM Corporation



## **Unit Summary**

Having completed this unit, you should be able to:

- ✔ Briefly describe 3270
- ✓ Access z/OS using TN3270 Emulator
- ✓ Access z/OS using SSH client (PuTTY)
- ✓ Access z/OS using FTP