




Prepared and published by the Defense Mapping Agency
Hydrographic/Topographic Center, Washington, D.C.

Scale 1:50,000

Meters 1000 500 0 1 2 3 4 5 Kilometers

1 1/2 0 1 2 3 Statute Miles

1 1/2 0 1 2 3 Nautical Miles

CONTOUR INTERVAL 20 METERS
SUPPLEMENTARY CONTOURS 10 METERS

INTERVALO DE CURVAS 20 METROS
CURVAS SUPLEMENTARIAS CADA 10 METROS

SPHEROID	CLARKE 1866	ESFEROIDE	CLARKE 1866
GRID	1,000 METERS UTM ZONE 16 (BLUE NUMBERED LINES)	GRILLA	TRANSVERSA DE MERCATOR A 1,000 METROS, ZONA 16 (LINEAS AZULAS NUMERADAS)
1,000 METER, LAHBERT GRID	1,000 METERS UTM ZONE 16 (BLACK NUMBERED LINES)	1,000 METER, LAHBERT GRID	1,000 METERS UTM ZONE 16 (BLACK NUMBERED LINES)
PROJECTION	TRANSVERSE MERCATOR	PROYECCION	TRANSVERSA DE MERCATOR
VERTICAL DATUM	MEAN SEA LEVEL	DATUM VERTICAL	NIVEL MEDIO DE MARE
HORIZONTAL DATUM	NORTH AMERICAN 1927 DATUM	DATUM HORIZONTAL	DATUM NORTEAMERICANO 1927
CONTROL BY	NATIONAL GEOGRAPHIC INSTITUTE	CONTROL POR	INSTITUTO GEOGRAFICO NACIONAL

Reprinted by NOAA 4-99

USERS SHOULD REFER CORRECTIONS, ADDITIONS, AND COMMENTS TO THE NIMA CUSTOMER HELP DESK: 1-800-455-0899; COMMERCIAL 314-260-5032; DSN 490-5032; OR WRITE TO: DIRECTOR, NATIONAL IMAGERY AND MAPPING AGENCY, ATTN: CDD, MAIL STOP P-37, 4800 SANGAMORE ROAD, BETHESDA, MD 20816-5003

SAMPLE 1,000 METER GRID SQUARE
EJEMPLO DEL CUADRADO DE 1,0 METROS

46

x Sample

100 METER REFERENCE

1. Read large numbers labeling the VERTICAL grid line left of point and estimate tenths (100 meters) from grid line to point. 12 3
2. Read large numbers labeling the HORIZONTAL

REFERENCIA DE 100 METROS

1. Léanse las cifras grandes correspondientes a la línea VERTICAL de la cuadrícula situada a la izquierda del punto y estimense los décimos (100 metros) entre la línea mencionada y el punto. 12 3

Example: 123456

línea HORIZONTAL de la cuadrícula situada debajo del punto y estimase los decimos (100 metros) entre la línea mencionada y el punto 45 6

Ejemplo: 123456

CUANDO SE HACE REFERENCIA A UN PUNTO AL OTRO LADO DE UNA LÍNEA DE 100,000 METROS, ANTERIORIDAD A LA REFERENCIA ANTERIORIDAD.

Example: GN123456

WHEN REPORTING OUTSIDE THE GRID ZONE DESIGNATION AREA, PREFIX THE GRID ZONE

CUANDO SE HACE REFERENCIA FUERA DEL ÁREA DE LA ZONA DESIGNADA DE CUADRÍCULA ANTE-

GRID CONVERGENCE
0°38' (11 MILS)
FOR CENTER OF SHEET

CONVERGENCIA DE LA CUADRÍCULA
0°38' (111 MILESIMAS)

TO CONVERT A
MAGNETIC AZIMUTH
TO A GRID AZIMUTH
ADD G-M ANGLE

TO CONVERT A
GRID AZIMUTH TO A
MAGNETIC AZIMUTH
SUBTRACT G-M ANGLE

GRID NORTH
NORTE DE CUADRICULA


TRUE NORTH
NORTE VERDADERO

1980
G-M ANGLE
2° (40 MILS)

1980
ÂNGULO C-M
2° (40 MILÉSIMAS)


PARA CONVERTIR UN
ACIMUT MAGNÉTICO A
ACIMUT DE LA CUADRÍCULA
SÚMESE EL ÁNGULO C

PARA CONVERTIR UN
ACIMUT DE LA CUADRÍCULA
ACIMUT MAGNÉTICO
RESTESE EL ÁNGULO α

ELEVATION GUIDE
GUÍA DE ELEVACIÓN

High	High
Medium	Medium
Low	Low

ADJOINING SHEETS
HOJAS ADYACENTES



BOUNDARIES
LÍMITES



GLOSSARY GLOSARIO

Departamento	first-order administrative division
Pinos	pine
Pinos Ralos	sparse pine
Rio	stream

LIMITED DISTRIBUTION Distribution authorized to DoD,
IAW 10 U.S.C. §§130 & 455. Release authorized to U.S. DoD contractors,
IAW 48 C.F.R. §252.245-7000. Refer other requests to Headquarters,
NIMA, ATTN: Release Officer, Step P-25. Destroy as "For Official Use Only."
Removal of this caveat is prohibited.

THIS MAP IS RED-LIGHT READABLE

NSN 7643014037665

ED. NO. 001