Table Of Contents

Fable Of Contents	1
nstall telnetd server	2
See also:	2

Install telnetd server 2/2

nixCraft: Linux Tips, Hacks, Tutorials, And Ideas In Blog Format http://www.cyberciti.biz/

Home > Faq > FAQ

Ubuntu Linux enable telnet service

Posted by Vivek Gite <vivek@nixcraft.com>

O. How do I install and start telnet service / server under Ubuntu Linux?

A. Telnet is an insecure service. It is recommended that you <u>use ssh service</u> [1]. However sometime telnet server or service is needed. Here are instructions to enable telnet:

Install telnetd server

\$ sudo apt-get install telnetd

Restart inetd service:

\$ sudo /etc/init.d/openbsd-inetd restart

You should now be able to telnet to the server from Windows or Linux desktop system to Ubentu Linux telnet server. Type the following command to connect to Telnet server:

```
$ telnet ubentu-linux-server-ip
$ telnet 192.168.1.200
$ telnet ubentu.mydomain.com
```

See also:

• FreeBSD/Fedora Core/Redhat/Debian Linux telnet server howto [2]

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our <u>daily email</u> newsletter or <u>weekly newsletter</u> to make sure you don't miss a single tip/tricks. Alternatively, subscribe via <u>RSS/XML</u> feed.

Article printed from Frequently Asked Questions About Linux / UNIX: http://www.cyberciti.biz/faq/

URL to article: http://www.cyberciti.biz/faq/ubuntu-linux-enable-telnet-service/

URLs in this post:

[1] use ssh service: http://www.cyberciti.biz/faq/ubuntu-linux-openssh-server-installation-and-configuration/

[2] FreeBSD/Fedora Core/Redhat/Debian Linux telnet server howto: http://www.cyberciti.biz/faq/how-do-i-turn-on-telnet-service-on-for-a-linuxfreebsd-system/

Copyright © 2006-2010 <u>nixCraft</u>. All rights reserved. This print / pdf version is for personal non-commercial use only. More details http://www.cyberciti.biz/tips/copyright.