

# Video preview button

Pause or resume an auto-played video preview.

- Overview
- Specs

|                 |                                                                                                                   |
|-----------------|-------------------------------------------------------------------------------------------------------------------|
| Figma component |  <a href="#">Open in Figma</a> |
| Status          | Healthy                                                                                                           |


Also known as: *Play/Pause button*, *Auto-play button*

Some components include video previews that start playing automatically when they come into view. For these auto-played videos, we use Media preview buttons, which allow users to pause or resume the preview. The button includes a progress circle that visually indicates how far along the video preview is. The Media preview button is always placed at the bottom-right corner of the video.

For regular videos that are not previews, use the [Media button](#).



## Anatomy




1. **Button fill:** In its default state, the semi-transparent `action-primary-default-onphoto` fill is applied to ensure accessibility on any video.
2. **Icon:** Displays the current video state (Play or Pause).
3. **Progress circle** (optional): Shows the remaining time for the video preview. This feature is optional and may be omitted if technical constraints prevent its implementation.
4. **Container:** An oversized container creates a large, accessible target area, making the button easy to tap or click.

## Variants

The Media preview button has two variants that represent the current state of the video:



- **Pause:** Displayed by default when the video is auto-playing. It allows users to pause the video preview.
- **Play:** Displayed after the video is paused. It allows users to resume the preview.



## Hierarchy


Playing or pausing a video preview is considered a secondary action. For this reason, the Media preview button uses the same visual style as [other secondary buttons](#), and is always placed in the bottom right corner of the video.

This ensures that the primary action, such as playing the full video, remains more prominent and draws the user's attention first.



✗ Don't

Don't make playing or pausing a preview a primary action.



✓ Do

Always use Media preview for secondary actions like playing or pausing a video preview.

# Behavior

By default, the button’s Pause variant is displayed, indicating that the video is currently playing.

- When clicked, the video pauses and the button switches to the Play variant. The progress circle stops animating.
- Clicking the Play button resumes the preview and returns the control to the Pause variant. The progress circle continues animating from where it left off.



Show more button  
Guidelines

Video preview button  
Specs

