

Script de config

TP 2.7.1

P2P-1

```
enable
configure terminal
interface Serial0/1/1
ip ospf cost 50
interface Serial0/2/0
ip ospf hello-interval 20
ip ospf dead-interval 80
router ospf 10
auto-cost reference-bandwidth 1000
network 10.0.0.0 0.0.0.3 area 0
network 10.0.0.8 0.0.0.3 area 0
network 10.0.0.12 0.0.0.3 area 0
end
```

P2P-2

```
enable
configure terminal
router ospf 10
log-adjacency-changes
passive-interface GigabitEthernet0/0/0
passive-interface GigabitEthernet0/0/1
auto-cost reference-bandwidth 1000
network 10.0.0.0 0.0.0.3 area 0
network 10.0.0.4 0.0.0.3 area 0
network 192.168.1.0 0.0.0.255 area 0
```

```
network 192.168.2.0 0.0.0.255 area 0
end
```

P2P-3

```
enable
configure terminal
router ospf 10
log-adjacency-changes
passive-interface GigabitEthernet0/0/0
auto-cost reference-bandwidth 1000
network 10.0.0.4 0.0.0.3 area 0
network 10.0.0.8 0.0.0.3 area 0
network 192.168.3.0 0.0.0.15 area 0
end
```

BC-1

```
nable
configure terminal
interface GigabitEthernet0/0/0
ip ospf priority 255
ip ospf 10 area 0
interface Serial0/1/0
ip ospf hello-interval 20
ip ospf dead-interval 80
ip ospf 10 area 0
router ospf 10
router-id 6.6.6.6
passive-interface Serial0/1/1
auto-cost reference-bandwidth 1000
default-information originate
ip route 0.0.0.0 0.0.0.0 Serial0/1/1
end
```

BC-2

```
enable
configure terminal
interface GigabitEthernet0/0/0
ip ospf 10 area 0
interface GigabitEthernet0/0/1
ip ospf 10 area 0
router ospf 10
router-id 5.5.5.5
passive-interface GigabitEthernet0/0/0
auto-cost reference-bandwidth 1000
end
```

BC-3

```
enable
configure terminal
interface GigabitEthernet0/0/0
ip ospf 10 area 0
interface GigabitEthernet0/0/1
ip ospf 10 area 0
router ospf 10
router-id 4.4.4.4
passive-interface GigabitEthernet0/0/0
auto-cost reference-bandwidth 1000
end
```

TP 5.1.8

Router R2

```
enable
configure terminal
```

```
interface GigabitEthernet0/0
 ip access-group 1 out
 access-list 1 deny 192.168.11.0 0.0.0.255
 access-list 1 permit any
 end
```

Router R3

```
enable
configure terminal
interface GigabitEthernet0/0
 ip access-group 1 out
 access-list 1 deny 192.168.10.0 0.0.0.255
 access-list 1 permit any
 end
```

TP 5.2.7

Router R1

```
enable
configure terminal
ip access-list standard BRANCH-OFFICE-POLICY
 permit host 192.168.30.3
 permit 192.168.40.0 0.0.0.255
interface g0/0/0
 ip access-group BRANCH-OFFICE-POLICY out
 ip access-list standard BRANCH-OFFICE-POLICY
 30 permit 209.165.200.224 0.0.0.31
 40 deny any
 end
```

Router R3

```
enable
configure terminal
access-list 1 remark Allow R1 LANs Access
access-list 1 permit 192.168.10.0 0.0.0.255
access-list 1 permit 192.168.20.0 0.0.0.255
access-list 1 deny any
interface g0/0/0
 ip access-group 1 out
end
```

TP 5.4.13

Router RT1

```
enable
configure terminal
ip access-list extended ACL
 deny tcp host 172.31.1.101 host 64.101.255.254 eq www
 deny tcp host 172.31.1.101 host 64.101.255.254 eq 443
 deny tcp host 172.31.1.101 host 64.103.255.254 eq www
 deny tcp host 172.31.1.101 host 64.103.255.254 eq 443
 deny tcp host 172.31.1.102 host 64.101.255.254 eq ftp
 deny tcp host 172.31.1.102 host 64.103.255.254 eq ftp
 deny icmp host 172.31.1.103 host 64.101.255.254
 deny icmp host 172.31.1.103 host 64.103.255.254
 permit ip any any
interface GigabitEthernet0/0
 ip access-group ACL in
end
```