

参数	描述	Default
<code>image</code>	Redis image	<code>bitnami/redis:{VERSION}</code>
<code>imagePullPolicy</code>	Image pull policy	<code>IfNotPresent</code>
<code>serviceType</code>	Kubernetes Service type	<code>ClusterIP</code>
<code>usePassword</code>	Use password	<code>true</code>
<code>redisPassword</code>	Redis password	Randomly generated
<code>args</code>	Redis command-line args	<code>[]</code>
<code>redisExtraFlags</code>	Redis additional command line flags	<code>[]</code>
<code>persistence.enabled</code>	Use a PVC to persist data	<code>true</code>
<code>persistence.path</code>	Path to mount the volume at, to use other images	<code>/bitnami</code>
<code>persistence.subPath</code>	Subdirectory of the volume to mount at	<code>""</code>
<code>persistence.existingClaim</code>	Use an existing PVC to persist data	<code>nil</code>
<code>persistence.storageClass</code>	Storage class of backing PVC	<code>generic</code>
<code>persistence.accessMode</code>	Use volume as ReadOnly or ReadWrite	<code>ReadWriteOnce</code>
<code>persistence.size</code>	Size of data volume	<code>8Gi</code>
<code>resources</code>	CPU/Memory resource requests/limits	Memory: 256Mi , CPU: 100m
<code>metrics.enabled</code>	Start a side-car prometheus exporter	<code>false</code>
<code>metrics.image</code>	Exporter image	<code>oliver006/redis_exporter</code>
<code>metrics.imageTag</code>	Exporter image	<code>v0.11</code>
<code>metrics.imagePullPolicy</code>	Exporter image pull policy	<code>IfNotPresent</code>

参数	描述	Default
<code>metrics.resources</code>	Exporter resource requests/limit	Memory: <code>256Mi</code> , CPU: <code>100m</code>
<code>nodeSelector</code>	Node labels for pod assignment	<code>{}</code>
<code>tolerations</code>	Toleration labels for pod assignment	<code>[]</code>
<code>networkPolicy.enabled</code>	Enable NetworkPolicy	<code>false</code>
<code>networkPolicy.allowExternal</code>	Don't require client label for connections	<code>true</code>
<code>service.annotations</code>	annotations for redis service	<code>{}</code>
<code>service.loadBalancerIP</code>	loadBalancerIP if service type is <code>LoadBalancer</code>	<code>''</code>
<code>securityContext.enabled</code>	Enable security context	<code>true</code>