

EJERCICIO 1

Router 1

```
Micro - GNS3
Control Node Annotations
R1

*Mar 1 00:07:13.599: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2/0, changed state to up
00147124R1(config)#end
00147124R1#
*Mar 1 00:07:30.319: %SYS-5-CONFIG_I: Configured from console by console
00147124R1#write memory
Building configuration...
[OK]
00147124R1#show ip interface brief
% Invalid input detected at '^' marker.

00147124R1#show ip interface brief
Interface IP-Address OK? Method Status Prot
FastEthernet0/0 10.25.82.1 YES manual up
FastEthernet0/1 10.20.82.65 YES manual up
FastEthernet1/0 10.25.82.97 YES manual up
FastEthernet2/0 10.25.82.121 YES manual up
```

```
[OK]
00147124R1#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 6 subnets, 5 masks
C 10.20.82.64/27 is directly connected, FastEthernet0/1
C 10.25.82.96/28 is directly connected, FastEthernet1/0
S 10.25.82.112/29 [1/0] via 10.25.82.126
C 10.25.82.120/30 is directly connected, FastEthernet2/0
S 10.25.82.124/30 [1/0] via 10.25.82.122
C 10.25.82.0/26 is directly connected, FastEthernet0/0
00147124R1#
```

Router 2

```
00147124R2(config-if)#no shutdown
00147124R2(config-if)#exit
00147124R2(config)#
*Mar 1 00:05:44.911: %LINK-3-UPDOWN: Interface FastEthernet0/0, changed state to up
*Mar 1 00:05:45.911: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
00147124R2(config)#interface fastEthernet0/1
00147124R2(config-if)#ip address 10.25.82.125 255.255.255.252
00147124R2(config-if)#no shutdown
00147124R2(config-if)#
*Mar 1 00:06:43.983: %LINK-3-UPDOWN: Interface FastEthernet0/1, changed state to up
*Mar 1 00:06:44.983: %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
00147124R2(config-if)#exit
00147124R2(config)#end
00147124R2#
*Mar 1 00:06:58.403: %SYS-5-CONFIG_I: Configured from console by console
00147124R2#write memory
Building configuration...
[OK]
00147124R2#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
00147124R2(config)#ip route 10.25.82.0 255.255.255.192 10.25.82.121
00147124R2(config)#ip route 10.25.82.64 255.255.255.224 10.25.82.121
00147124R2(config)#ip route 10.25.82.96 255.255.255.240 10.25.82.121
00147124R2(config)#ip route 10.25.82.112 255.255.255.248 10.25.82.126
00147124R2(config)#end
00147124R2#
*Mar 1 00:24:21.439: %SYS-5-CONFIG_I: Configured from console by console
00147124R2#write memory
Building configuration...
[OK]
00147124R2#show ip interface brief
Interface IP-Address OK? Method Status Protocol
FastEthernet0/0 10.25.82.122 YES manual up
FastEthernet0/1 10.25.82.125 YES manual up
00147124R2#
```

```
FastEthernet0/1 10.25.82.125 YES manual up up
00147124R2#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 6 subnets, 5 masks
S    10.25.82.64/27 [1/0] via 10.25.82.121
S    10.25.82.96/28 [1/0] via 10.25.82.121
S    10.25.82.112/29 [1/0] via 10.25.82.126
C    10.25.82.120/30 is directly connected, FastEthernet0/0
C    10.25.82.124/30 is directly connected, FastEthernet0/1
S    10.25.82.0/26 [1/0] via 10.25.82.121
00147124R2#
```

solarwinds | Solar-PuTTY free tool © 2019-2023 Sc

Roter 3

```
Building configuration...
[OK]
00147124R3#show ip interface brief

```

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	10.25.82.113	YES	manual	up	up
FastEthernet0/1	10.25.82.126	YES	manual	up	up

```
00147124R3#
```

solarwinds | Solar-PuTTY free tool © 2019-2023 SolarWinds Worldwide

```
FastEthernet0/1 10.25.82.126 YES manual up up
00147124R3#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 6 subnets, 5 masks
S    10.25.82.64/27 [1/0] via 10.25.82.121
S    10.25.82.96/28 [1/0] via 10.25.82.121
C    10.25.82.112/29 is directly connected, FastEthernet0/0
S    10.25.82.120/30 [1/0] via 10.25.82.125
C    10.25.82.124/30 is directly connected, FastEthernet0/1
S    10.25.82.0/26 [1/0] via 10.25.82.121
00147124R3#
```



solarwinds | Solar-PuTTY free tool © 2019-2023 SolarWinds Worldwide, LLC. All rights reserved.

```
de Ann... PC1
10.25.82.112 icmp_seq=4 timeout
10.25.82.112 icmp_seq=5 timeout

PC1> show ip

NAME       : PC1[1]
IP/MASK    : 10.25.82.2/26
GATEWAY    : 10.25.82.1
DNS        :
MAC        : 00:50:79:66:68:00
LPORT      : 10028
RHOST:PORT : 127.0.0.1:10029
MTU        : 1500

PC1>
```



```
ode Anne
PC4
Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Meng (mirnshi@gmail.com)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

Checking for duplicate address...
PC1 : 10.25.82.114 255.255.255.248 gateway 10.25.82.113

PC4> show ip

NAME      : PC4[1]
IP/MASK    : 10.25.82.114/29
GATEWAY    : 10.25.82.113
DNS        :
MAC        : 00:50:79:66:68:03
LPORT     : 10034
RHOST:PORT : 127.0.0.1:10035
MTU        : 1500

PC4> 
```