

Filename: cisco-ccna200301-2-6-2-cisco_wireless_architectures

ShowName: Cisco CCNA (200-301)

Topic: 2.0 Network Access

EpisodeName: Cisco Wireless Architecture

Description: In this episode, you will learn about Cisco wireless architectures and AP modes. You will review the basic architecture for setting up a wireless network and review some of the modes that APs can be put into through the WLC (Wireless LAN Controller).

Cisco Wireless Architecture

2.6 Compare Cisco Wireless Architectures and AP modes

Wireless Architectures

- Infrastructure Mode
- Ad Hoc Mode
- Controller Architecture

AP modes (Lightweight Access Point modes)

```
Code starts
(Cisco controller)>config ap mode ?
Local Local mode for the Cisco AP
bridge Bridge mode for the Cisco AP
flexconnect flexconnect mode for the Cisco AP
monitor Monitor mode for the Cisco AP
reap Remote Edge AP (REAP) for the Cisco AP
rogue Rogue Detector mode for the Cisco AP
se-connect Spectrum Expert Only Connect mode for Cisco AP
sniffer Wireless Sniffer mode for the Cisco AP
Code ends
```

- Local mode: Default mode. Requires a WLC to operate
- bridge: bridges wireless and wired infrastructure together
- flexconnect: addresses scalability and relaxes the dependency on the WLC
e.g. 2 different SSIDs can be directed differently.
Datapath (guest ssid vs local ssid) (Authentication (RADIUS and Local))
- monitor: puts APs into mode that doesn't handle wireless traffic but act as sensors for location, rogue access points, and intrusion detection.
- H-REAP mode: addresses scalability and relaxes the dependency on the WLC (older mode renamed flex connect)
- Rogue: detects rogue access points and clients connected to it. Switch needs to send the MAC clients to the Rogue Detector. The RD sends them to the WLC compares that to what the WLC has learned from the directly connected APs (authorized).
- se-connect mode: use to gather RF information around the AP. Does not service clients or broadcasts an SSID
- sniffer mode: AP works a sniffer to capture and forward all the packets on a particular channel to a remote machine that runs Airopeek. These packets contain information on timestamp, signal strength, packet size and so on. The sniffer feature can be enabled only if you run Airopeek--a third-party network analyzer software that supports decoding of data packets.