FF_SAVEBORR_GRID Example for Generating Asset Grid

back to Fan's Intro Math for Econ, Matlab Examples, or Dynamic Asset Repositories

This is the example vignette for function: **ff_saveborr_grid** from the **MEconTools Package.** This function generates variously spaced savings/borrowing states/choices grid.

Test FF_SAVEBORR_GRID Defaults


Call the function with defaults.


	(XXXXXXXXXXX											
	NAME: mp_c					(etc)						
xxxxxxxxx	(XXXXXXXXXX	i i	xxxxxx idx	xxxxxxxx ndim	numel	nouM	colN	CIIM	moan	c+d	coefvari	min
		1	IUX	патш	пишет	rowN	COTIN	sum	mean	std	COETVALI	IIITI
		_										
ar_fl_	saveborr	1	1	2	25	25	1	385.93	15.437	15.324	0.99265	1
xxx TABLE:	ar_fl_save	borr x	xxxxx	xxxxxxx	xxx							
	c1											
r1	1											
r2	1.0174											
r3	1.0982											
r4	1.2707											
r5	1.5557											
r6	1.9707											
r7	2.5312											
r8	3.2512											
r9	4.1434											
r10	5.2196											
r11	6.4912											
r12	7.9687											
r13	9.6621											
r14 r15	11.581 13.735											
r16	16.132											
r17	18.781											
r18	21.691											
r19	24.87											
r20	28.324											
r21	32.063											
r22	36.093											
r23	40.421											
r24	45.054											
r25	50											
	XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX											
	(XXXXXXXXXXX											
			i	idx	value							
			_									
anid a	evenlog_thr	ochold	1	2	1							
	log10space_		2	3	0.3							
8, Tn_1	.og_ospace_	_^_	_	ر	0.5							

Test FF_SAVEBORR_GRID Default Linear Grid, Log Grid, Power Grid, Threshold Grid

Call the function with defaults.

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
% Four types of grid points
st_grid_type = 'grid_linspace';
[ar fl saveborr linspace] = ff saveborr grid(fl a min, fl a max, it a points, st grid type);
st grid type = 'grid log10space';
[ar fl saveborr log10space] = ff saveborr grid(fl a min, fl a max, it a points, st grid type);
st_grid_type = 'grid_powerspace';
[ar_fl_saveborr_powerspace] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
st_grid_type = 'grid_evenlog';
[ar_fl_saveborr_evenlog] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type);
% draw four types of lines jointly
mt value = [ar_fl_saveborr_linspace'; ar_fl_saveborr_log10space'; ...
    ar_fl_saveborr_powerspace'; ar_fl_saveborr_evenlog'];
ar_row_grid = ["grid linspace", "grid log10space", "grid powerspace", "grid evenlog"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp support graph('cl st graph title') = {'Four Asset Grids with Default Parameters'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);
```







Test FF_SAVEBORR_GRID Log Grid Changing Parameters

Log grid, same min and max, change log X1 and X2 points

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_log10space';
% Four types of grid points
mp_grid_control = containers.Map('KeyType','char', 'ValueType','any');
mp_grid_control('grid_log10space_x1') = 0.1;
mp_grid_control('grid_log10space_x2') = 1;
[ar_fl_log10space_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_log10space_x1') = 0.1/2;
mp_grid_control('grid_log10space_x2') = 1*2;
[ar_fl_log10space_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_log10space_x1') = 0.1/4;
mp_grid_control('grid_log10space_x2') = 1*4;
[ar_fl_log10space_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_log10space_x1') = 0.1/6;
mp_grid_control('grid_log10space_x2') = 1*6;
[ar_fl_log10space_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
% draw four types of lines jointly
mt_value = [ar_fl_log10space_a'; ar_fl_log10space_b'; ...
    ar_fl_log10space_c'; ar_fl_log10space_d'];
ar_row_grid = [...
    "log10space:x1=0.1/1, x2=1", ...
    "log10space:x1=0.1/2, x2=2", ...
    "log10space:x1=0.1/4, x2=3", ...
    "log10space:x1=0.1/6, x2=4"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Log 10 Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
```

```
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);
```







Test FF_SAVEBORR_GRID Power Grid Changing Parameters

Log grid, same min and max, change log X1 and X2 points

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_powerspace';
% Four types of grid points
mp_grid_control = containers.Map('KeyType','char', 'ValueType','any');
mp_grid_control('grid_powerspace_power') = 1;
[ar_fl_powerspace_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_mp_grid_control('grid_powerspace_power') = 2;
```

```
[ar_fl_powerspace_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_powerspace_power') = 4;
[ar_fl_powerspace_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
mp_grid_control('grid_powerspace_power') = 6;
[ar_fl_powerspace_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_
% draw four types of lines jointly
mt_value = [ar_fl_powerspace_a'; ar_fl_powerspace_b'; ...
    ar_fl_powerspace_c'; ar_fl_powerspace_d'];
ar_row_grid = [...
    "powerspace:power=1", ...
    "powerspace:power=2", ...
    "powerspace:power=4", ...
    "powerspace:power=6"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Power Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff_graph_grid(mt_value, ar_row_grid, ar_col_grid, mp_support_graph);
```





Test FF_SAVEBORR_GRID Threshold Grid Changing Parameters

Threshold Grid, Changing Threshold Levels. Initial segments below threshold are linspace, then logspace.

```
% Same min and max and grid points
[fl_a_min, fl_a_max, it_a_points] = deal(0,50,25);
st_grid_type = 'grid_evenlog';
% Four types of grid points
mp_grid_control = containers.Map('KeyType','char', 'ValueType','any');
mp_grid_control('grid_evenlog_threshold') = 0.50;
[ar_fl_evenlog_a] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_cor
mp_grid_control('grid_evenlog_threshold') = 1.00;
[ar_fl_evenlog_b] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_cor
mp_grid_control('grid_evenlog_threshold') = 2;
[ar_fl_evenlog_c] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_cor
mp_grid_control('grid_evenlog_threshold') = 5;
[ar_fl_evenlog_d] = ff_saveborr_grid(fl_a_min, fl_a_max, it_a_points, st_grid_type, mp_grid_cor
% draw four types of lines jointly
mt_value = [ar_fl_evenlog_a'; ar_fl_evenlog_b'; ...
    ar_fl_evenlog_c'; ar_fl_evenlog_d'];
ar_row_grid = [...
    "evenlog:threshold=0.5", ...
    "evenlog:threshold=1.0", ...
    "evenlog:threshold=2.0", ...
    "evenlog:threshold=5.0"];
ar_col_grid = 1:it_a_points;
mp_support_graph = containers.Map('KeyType', 'char', 'ValueType', 'any');
mp_support_graph('cl_st_graph_title') = {'Asset Grids with Threshold Grid Varying Controls'};
mp_support_graph('cl_st_ytitle') = {'Asset Grid Points'};
mp_support_graph('cl_st_xtitle') = {'Asset Grid Counter'};
mp_support_graph('bl_graph_logy') = true; % do not log
ff graph grid(mt value, ar row grid, ar col grid, mp support graph);
```

