



SSH - TELNET

```
ROUTER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#Interface ethernet 0/0
ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Aug 19 02:53:50.817: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
Interface      IP-Address      OK? Method Status  Prot
ccol
Ethernet0/0    50.0.0.1        YES manual up      up
Ethernet0/1    unassigned      YES TFTP  down    down
Ethernet0/2    unassigned      YES TFTP  down    down
Ethernet0/3    unassigned      YES TFTP  down    down
ROUTER#
```

```
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#username console password console  
ROUTER(config)#line console 0  
ROUTER(config-line)#password testconsole  
ROUTER(config-line)#login local  
ROUTER(config-line)#exit  
ROUTER(config)#show ip interface breif  
^  
% Invalid input detected at '^' marker.  
ROUTER(config)#
```

ROUTER

```
ROUTER(config)#  
ROUTER(config)#enable secret enable  
ROUTER(config)#  
ROUTER(config)#line vty 0 4  
ROUTER(config-line)#transport input telnet  
ROUTER(config-line)#password telnet  
ROUTER(config-line)#login  
ROUTER(config-line)#exit  
ROUTER(config)#  
ROUTER(config)#  
ROUTER(config)#
```


QEMU (Win)



Computer

Cisco IP
Communic...

Recycle Bin

Control Panel

PuTTY

http://

PuTTY Configuration

Category:

- Session
 - Logging
- Terminal
 - Keyboard
 - Bell
 - Features
- Window
 - Appearance
 - Behaviour
 - Translation
 - Selection
 - Colours
- Connection
 - Data
 - Proxy
 - Telnet
 - Plugin
 - SSH
 - Serial

Basic options for your PuTTY session

Specify the destination you want to connect to

Host Name (or IP address)	Port
50.0.0.1	23

Connection type:
☐ Raw ☒ Telnet ☐ Rlogin ☐ SSH ☐ Serial

Load, save or delete a stored session

Saved Sessions

Default Settings	Load
	Save
	Delete

Close window on exit:
☐ Always ☐ Never ☒ Only on clean exit

About Help Open Cancel

3:33 AM

QEMU (Win)



50.0.0.1 - PuTTY

User Access Verification

Password:

Password:

ROUTER>

► ROUT

Tftpd32