
Kali

It is easier to install Kali VMWare versions. Then in VMWare Workstation, open downloaded **kali.vmx** virtual machine. Need to configure this virtual machine **Network Adapter** as following capture. default username and password are both **kali**.




Metasploitable Server

Download metasploitable-linux-2.0.0.zip from below sourceforge Link: https://sourceforge.net/projects/metasploitable-linux-2.0.0.zip/download

1. Open unzipped virtual machines, and configure as follows, can delete Network Adapter: Hostonly.

default username and password are both msfadmin



Finally, get the IP address under subnet 192.168.1.x/24

```
To access official Ubuntu documentation, please visit:
http://help.ubuntu.com/
No mail.
msfadmin@metasploitable:~$ ifconfig
eth0
          Link encap:Ethernet HWaddr 00:0c:29:e8:1f:7c
          inet addr:192.168.1.10 Bcast:192.168.1.255 Mask:255.255.255.0 inet6 addr: fe80::20c:29ff:fee8:1f7c/64 Scope:Link
          UP BROADCAST RUNNING MULTICAST MTU:1500 Metric:1
          RX packets:37 errors:0 dropped:0 overruns:0 frame:0
          TX packets:66 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:4133 (4.0 KB) TX bytes:6891 (6.7 KB)
          Interrupt:17 Base address:0x2000
lo
          Link encap:Local Loopback
          inet addr:127.0.0.1 Mask:255.0.0.0
          inet6 addr: ::1/128 Scope:Host
          UP LOOPBACK RUNNING MTU: 16436 Metric: 1
          RX packets:91 errors:0 dropped:0 overruns:0 frame:0
          TX packets:91 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:19301 (18.8 KB) TX bytes:19301 (18.8 KB)
nsfadmin@metasploitable:~$
```

This Metasploitable server can be accessed by typing IP address in the Browser search bar



Warning: Never expose this VM to an untrusted network!

Contact: msfdev[at]metasploit.com

Login with msfadmin/msfadmin to get started

- TWiki phpMyAdmin Mutillidae DVWA WebDAV