releases

System and OS Requirements:

- 1. Windows 10 and above
- 2. Minimum 2 cores
- 3. 2GB RAM
- 4. 30GB SSD
- 5. Java version 8 and above must be installed in your VPS (version 16 suggested). If your windows VPS doesn't have it download it from Here and set java in your windows environment.

Installing and configuring a FFS Blockchain full node for FFT mining on a Windows PC/VPS

- Step 1: Click Here and Download the Zip Folder and Unzip it.
- Step 2: Modify the configuration file to activate your node in mainnet.conf
- Step 3: Click the file inside the folder named as "start.bat"

How to run an FFT Node of the FFS Blockchain

- **Step 1:** Download the FFT Desktop Wallet and set mainnet inside the FFT wallet to generate a blank FFT account. (without funds)
- **Step 2:** Notedown the Encoded seed from your FFT wallet account, looking inside the settings. (It will be required for the edits to be done inside the mainnet.conf file)
- **Step 3:** Open the mainnet.conf file in any text editor. (Text Note, NotePad etc)
- Step 4: Change the below lines inside the mainnet.conf file and save it
- a) node-name = "Type Your Node Name Here"
- b) declared-address = "127.0.0.1:6860" #declared ip address of your node
- c) seed = "Enter Your Encoded Backup Seed Here Of Your FFT Wallet Account"
- d) password = "Your Password Here" #Enter a 15 words any Strong password to protect your Wallet
- e) save the mainnet.conf file after making above changes
- f) run the file start.bat by double clicking it and the node should start downloading the blocks to get in synch with the FFS Blockchain.

Installing and configuring a FFS Blockchain full node for FFT mining on a Linux PC/Server

System and OS Requirements:

- 1. Ubuntu 18 VPS in case of Linux
- 2. Minimum 2 cores
- 3. 2GB RAM
- 4. 30GB SSD

How to run an FFT Node of the FFS Blockchain

All commands are issued as root. If you do not use your root account most commands would probably require 'sudo' to work. Eg. "sudo apt update"

Step 1: login into you Linux pc/server terminal with the root account

Step 2: Type the command showed below

apt update

Step 3: Install the Java development kit using the following commands

sudo apt install openjdk-8-jre sudo apt install openjdk-8-jdk sudo apt update

Once its installed check if the version is the latest.

java -version

Step 4: Download the latest fullnode from Food-Forest-Sardegna repository.

Link: Latest Release

Command to download it on your Linux PC/Server

sudo wget https://github.com/Food-Forest-Sardegna/release/archive/refs/heads/main.zip

Step 5: Download the FFT Desktop Wallet in Linux pc, create a new account inside the Mainnet chain and save your Encoded backup seed found inside the settings, to use it inside mainnet.conf when needed.

Type the commands below, and press the "Enter" button after each of them, to install Unzip in your Linux pc/server and being able next to make the required changes in the mainnet.conf file

sudo apt-get install unzip unzip master.zip cd releases-master screen

sudo vi mainnet.conf

Press the Enter button to enable the ability to type and edit the file with vi editor

Step 6: Change the lines below inside the mainnet.conf file and save them as explained

- a) node-name = "Type Your Node Name Here"
- b) declared-address = "127.0.0.1:6860" #declared ip address of your node
- c) seed = "Enter Your Encoded Backup Seed Here From FFT Wallet"
- d) password = "Your Password Here" #Enter the 15 words any Strong password to protect your Wallet
- e) use the commands below to save the channges inside the mainnet.conf file

Press the Escape (Esc) button and type the below command

:w

Next press the Enter button.

Note: if something went wrong during the editing or you don't wanna to save it, just press escape and type :qa! to exit by pressing the Enter button after. Use the command sudo vi mainnet.conf again to edit the file if necessary.

Now to start the node simply use the following command:

java -jar fft-all-1.3.6.jar mainnet.conf

The node will start downloading and synching the blockchain. If any error appears during the activation of the node means something has been inserted wrongly in the mainnet.conf file. Use the "Note" indications to edit the file again.

When all blocks are synched, then you can detach the screen by pressing CTRL+d and close the window. The node has been set to run in background process of your Linux PC/VPS.

Good Luck and Enjoy the Mining and Leasing of FFT.