

The Document Build


document-assembly · built in n8n

The document with a blank merge field is the one that goes out to a client.

What it connects to: Every merge field is a read from another system. A document that assembles before its source has answered is how blanks reach a client.

1 of 4 SYSTEM

Here's the assembly, which verifies every merge field resolved before anything sends.



2 of 4 THINKING

If one is missing it holds the document and names the field, rather than sending a hole.

The screenshot displays the Node-RED web interface with a node titled "Did every merge field resolve?". The interface is divided into three main sections: INPUT, Parameters, and OUTPUT.

INPUT: Shows "No input data" with a button "Execute previous nodes" and the text "to view input data".

Parameters: Contains configuration options for the node.


- Conditions:** A text area contains the JSON condition: `{{ $json.allFieldsResolved === true && $json.missingFields.length === 0 }}`. A dropdown menu is set to "is true". Below the text area is a "+ Add condition" button.
- Options:** A toggle switch for "Convert types where required" is currently turned off. Below it is a "+ Add option" button.
- Buttons:** An orange "Execute step" button is located at the top right of the Parameters section.

OUTPUT: Shows "No output data" with a button "Execute step" and the text "to view output data".

At the bottom of the interface, there is a "Logs" tab and a feedback prompt: "I wish this node would..."

3 of 4 THEIR-WORLD

The paper trail that goes with it — every document generated is traceable back to the record it came from.



4 of 4 RESULT

And the retry configuration on the generation call, so a slow storage API delays a document instead of losing one.

The screenshot displays the n8n workflow editor interface. The top bar shows the workflow title "Pull the record the document describes" and a tab for "Settings". The "Execute step" button is visible in the top right of the settings panel.

The interface is divided into three main sections:

- INPUT:** Displays "No input data" and a button "Execute previous nodes" with the text "to view input data" below it.
- Parameters:** Contains various configuration options for the HTTP Request node:
 - SSL Certificates:** Toggle switch (off).
 - Always Output Data:** Toggle switch (off).
 - Execute Once:** Toggle switch (off).
 - Retry On Fail:** Toggle switch (on, highlighted in green).
 - Max. Tries:** Input field set to 3.
 - Wait Between Tries (ms):** Input field set to 2000.
 - On Error:** Dropdown menu set to "Continue (using error output)".
 - Notes:** A text area for adding notes.
 - Display Note in Flow?:** Toggle switch (off).
- OUTPUT:** Displays "No output data" and a button "Execute step" with the text "or set mock data" below it. A tooltip above the button states: "This node will automatically retry if it fails" and "Execution will continue even if the node fails".

At the bottom of the settings panel, it indicates "HTTP Request node version 4.2 (Latest version: 4.5)" and a link "I wish this node would...".