

The Win-Back


reactivation · built in n8n

Customers stop buying and nobody notices, because nothing is watching their own rhythm.

What it connects to: Dormancy is a purchase-history question and the message is a marketing-tool question. Neither system holds both halves.

1 of 4 SYSTEM

Here's the win-back, keyed on each customer's normal gap rather than a blanket 90 days.



2 of 4 THINKING

One honest message, never a series — that's what keeps it out of the spam folder.

The screenshot displays the Node-RED interface with a workflow step titled "Are they genuinely overdue for them?". The interface is divided into three main sections: INPUT, Parameters, and OUTPUT.

INPUT Section: Displays "No input data" and includes a button "Execute previous nodes" with the text "to view input data" below it.

Parameters Section: Contains tabs for "Parameters" and "Settings". Under the "Parameters" tab, there is a "Conditions" section with a text input field containing the JSON condition: `{{ $json.overdue === true && $json.sinceDays > ($json.normalGap * 1.5) }}`. A dropdown menu next to it is set to "is true". Below the conditions is a toggle switch for "Convert types where required" which is currently turned off. There is also an "Options" section with a "+ Add option" button.

OUTPUT Section: Displays "No output data" and includes a button "Execute step" with the text "to view output data" below it.

At the bottom of the interface, there is a "Logs" tab and a suggestion text: "I wish this node would...".

3 of 4 RESULT

And the branch that stops the moment someone replies.

The screenshot displays the Node-RED web interface with a dark theme. The top bar shows the workspace title "Work out their normal gap" and a "Docs" link. The interface is divided into three main panels: INPUT, Parameters/Settings, and OUTPUT.

INPUT Panel: Displays "No input data" with a button "Execute previous nodes" and the text "to view input data".

Parameters/Settings Panel: Contains the following configuration options:

- SSL Certificates:** Disabled (toggle off)
- Always Output Data:** Disabled (toggle off)
- Execute Once:** Disabled (toggle off)
- Retry On Fail:** Enabled (toggle on, green)
- Max. Tries:** 3
- Wait Between Tries (ms):** 2000
- On Error:** Continue (using error output)
- Notes:** A text area for notes.
- Display Note in Flow?:** Disabled (toggle off)

At the bottom of this panel, it says "HTTP Request node version 4.2 (Latest version: 4.5)" and a link "I wish this node would...".

OUTPUT Panel: Displays "No output data" with a button "Execute step" and the text "or set mock data". Above this, there are two informational messages:

- "This node will automatically retry if it fails"
- "Execution will continue even if the node fails"

On the left side, there is a vertical toolbar with various icons for adding nodes and managing the workspace. The bottom status bar shows "Logs".

4 of 4 MORE

And the branch that stops the moment someone replies.

The screenshot displays a workflow editor interface with a dark theme. At the top, a node is titled "Deduplicate on customer_id". Below the title, there are tabs for "Parameters" and "Settings", and an "Execute step" button. The "Parameters" tab is active, showing a "Mode" dropdown set to "Run Once for All Items" and a "Language" dropdown set to "JavaScript". Below these, there is a "JavaScript" section with a "Code" tab and an "Ask AI" button. The code editor contains the following JavaScript code:

```
1 // The same event arrives twice more often than anyone expects.
2 const key = $json["customer_id"];
3 const seen = $getWorkflowStaticData('global');
4 seen.keys = seen.keys || {};
5 const isNew = !seen.keys[key];
6 seen.keys[key] = Date.now();
7 return [{ json: { ...$json, isNew, dedupeKey: key } }];
```

Below the code editor, there is a tooltip that reads: "Type \$ for a list of special vars/methods. Debug by using console.log() statements and viewing their output in the browser console." The interface is divided into three main sections: "INPUT" on the left, "OUTPUT" on the right, and a central code editor. The "INPUT" section shows "No input data" and a button "Execute previous nodes" with the text "to view input data" below it. The "OUTPUT" section shows "No output data" and a button "Execute step" with the text "or set mock data" below it. At the bottom of the interface, there is a "Logs" section.