

The Onboarding Build


client-onboarding · built in n8n

The first 48 hours set the tone for the whole engagement, and they're usually improvised.

What it connects to: Won in the CRM has to become tasks in the project tool, a folder somewhere, and an intake the client actually returns. Three systems, one moment.

1 of 4 SYSTEM

Here's what fires the moment a deal flips to Won — welcome, checklist, intake, escalation.



2 of 4 THINKING

It escalates if the intake hasn't come back by day two, rather than waiting for someone to notice.

The screenshot displays a workflow editor with a central configuration panel and two side panels labeled 'INPUT' and 'OUTPUT'.

Central Panel:

- Title:** Did the intake come back inside two days?
- Tabs:** Parameters (selected), Settings
- Execute step:** A prominent orange button.
- Conditions:**
 - Expression: `{{ $json.intakeReturned === true && $json.n.dayCount <= 2 }}`
 - Dropdown: is true
 - + Add condition
 - ☐ Convert types where required
 - Options: + Add option
- Footer:** ? I wish this node would...

INPUT Panel:

- Icon: →|
- Text: No input data
- Button: Execute previous nodes
- Text: to view input data


OUTPUT Panel:

- Icon: |→
- Text: No output data
- Button: Execute step
- Text: to view output data

Bottom Bar: Logs

3 of 4 THEIR-WORLD

Running in the CRM, triggered on the status change rather than a stage drag.



4 of 4 MORE

And the onboarding assets it assembles.

The screenshot displays the Node-RED web interface with a dark theme. The top bar shows the title "Assemble what we already know about them" and a "Docs" link. The interface is divided into three main panels: INPUT, Parameters/Settings, and OUTPUT.

INPUT Panel: Displays "No input data" with a button "Execute previous nodes" and the text "to view input data".

Parameters/Settings Panel: Contains the following settings:

- SSL Certificates:** Toggle switch (off).
- Always Output Data:** Toggle switch (off).
- Execute Once:** Toggle switch (off).
- Retry On Fail:** Toggle switch (on, highlighted in green).
- Max. Tries:** Input field with the value "3".
- Wait Between Tries (ms):** Input field with the value "2000".
- On Error:** Dropdown menu set to "Continue (using error output)".
- Notes:** A large text area for notes.
- Display Note in Flow?:** Toggle switch (off).

At the bottom of this panel, it says "HTTP Request node version 4.2 (Latest version: 4.5)" and a link "I wish this node would...".

OUTPUT Panel: Displays "No output data" with a button "Execute step" and the text "or set mock data". Above this, there is a box containing two informational messages:

- ⚙️ This node will automatically retry if it fails
- ➔ Execution will continue even if the node fails

On the left side of the interface, there is a vertical toolbar with various icons for node management. On the right side, there are icons for refreshing the page and navigating between tabs.