

The Upsell Engine


storefront-upsell · built in n8n

Every order that ships without its obvious companion is margin you already paid to acquire.

What it connects to: The store knows the order. The email tool knows the person. The companion mapping belongs to neither, so it needs a home that both can read.

1 of 4 SYSTEM

Here's the system that decides whether there's an honest companion — and stays silent when there isn't.



2 of 4 THINKING

The restraint is the product: one suggestion, never a second, and never something they already own.

 Is there an honest companion product?

INPUT

→|

ParametersSettings

Execute step

Conditions

fx

```
{{ $json.companion != null && $json.companion.inStock && !$json.alreadyOwned }}
```

☒ is true

+ Add condition


☐ Convert types where required

Options

+ Add option

3 of 4 THEIR-WORLD

Running inside Shopify, with the companion mapping configured against the real catalogue.



4 of 4 MORE

And the cross-sell rule firing on the order itself.

The screenshot displays the Apache NiFi web console interface. The top navigation bar shows the title "Read the catalogue and the order history" and a "Docs" link. The main interface is divided into three panels: INPUT, Parameters/Settings, and OUTPUT.

INPUT Panel: Displays "No input data" with a button "Execute previous nodes" and the text "to view input data".

Parameters/Settings Panel: Contains the following configuration options:

- SSL Certificates:** Toggle switch (off).
- Always Output Data:** Toggle switch (off).
- Execute Once:** Toggle switch (off).
- Retry On Fail:** Toggle switch (on, highlighted in green).
- Max. Tries:** Input field with value "3".
- Wait Between Tries (ms):** Input field with value "2000".
- On Error:** Dropdown menu set to "Continue (using error output)".
- Notes:** A large text area for notes.
- Display Note in Flow?:** Toggle switch (off).

At the bottom of the Parameters/Settings panel, it shows "HTTP Request node version 4.2 (Latest version: 4.5)" and a link "I wish this node would...".

OUTPUT Panel: Displays "No output data" with a button "Execute step" and the text "or set mock data". Above this, there are two informational messages: "This node will automatically retry if it fails" and "Execution will continue even if the node fails".

The bottom of the interface features a "Logs" tab.