

The Document Build


document-assembly · built in n8n

The document with a blank merge field is the one that goes out to a client.

What it connects to: Every merge field is a read from another system. A document that assembles before its source has answered is how blanks reach a client.

1 of 4 SYSTEM

Here's the assembly, which verifies every merge field resolved before anything sends.



2 of 4 THINKING

If one is missing it holds the document and names the field, rather than sending a hole.

The screenshot displays the Node-RED web interface with a node titled "Did every merge field resolve?". The interface is divided into three main sections: INPUT, Parameters, and OUTPUT.

INPUT: Shows "No input data" with a button "Execute previous nodes" and the text "to view input data".

Parameters: Contains configuration options for the node.


- Conditions:** A text area contains the JSON condition: `{{ $json.allFieldsResolved === true && $json.missingFields.length === 0 }}`. A dropdown menu is set to "is true". Below the text area is a "+ Add condition" button.
- Options:** A toggle switch for "Convert types where required" is currently turned off. Below it is a "+ Add option" button.
- Buttons:** An orange "Execute step" button is located at the top right of the Parameters section.

OUTPUT: Shows "No output data" with a button "Execute step" and the text "to view output data".

At the bottom of the interface, there is a "Logs" tab and a feedback prompt: "I wish this node would..."

3 of 4 THEIR-WORLD

The paper trail that goes with it — every document generated is traceable back to the record it came from.



4 of 4 RESULT

And the retry configuration on the generation call, so a slow storage API delays a document instead of losing one.

The screenshot displays the n8n workflow editor interface. The top bar shows the workflow title "Pull the record the document describes" and a tab for "Settings". The "Execute step" button is visible in the top right of the settings panel.

The interface is divided into three main sections:

- INPUT:** Displays "No input data" and an "Execute previous nodes" button to view input data.
- Parameters / Settings:** Contains configuration options for the HTTP Request node:
 - SSL Certificates:** Disabled.
 - Always Output Data:** Disabled.
 - Execute Once:** Disabled.
 - Retry On Fail:** Enabled (indicated by a green toggle).
 - Max. Tries:** Set to 3.
 - Wait Between Tries (ms):** Set to 2000.
 - On Error:** Set to "Continue (using error output)".
 - Notes:** A text area for adding notes.
 - Display Note in Flow?:** Disabled.
- OUTPUT:** Displays "No output data" and an "Execute step" button. It also includes a link to "set mock data".

At the bottom of the settings panel, it indicates "HTTP Request node version 4.2 (Latest version: 4.5)" and a link to "I wish this node would...".