
Skip to content **Get Extensions**

The Get Extensions section lets you install and manage extensions preferences.



Blender Preferences Extensions section.

See also

To learn about extensions and how to create them, refer to the Extensions page.

Installing Extensions

There are different ways to install an extension:

Install from the Website

Drag the installation URL into Blender.

Install from Blender

Search for the extension name and click on Install.

Install from Disk

Use the drop-down menu in the top right, or drag-and-drop an extension . zip package into Blender.

Note

Any installed extension can be removed. This is a permanent change, though. To stop an extension temporarily, it is better to Disable it instead.

Updating Extensions

You need to manually check for available updates. Once an update is found, Blender will let you update any of the available extensions.

The current available version of an extension on the repository will always be considered the latest version.

Enable/Disable

Once an extension is installed it can be disabled (or re-enabled) as part of the user preferences. Some extension types do not support this, and will alway be shown as enabled.

Tip

If the Add-on does not activate when enabled, check the Console window for any errors that may have occurred.

Extension Settings

Visit Extensions Platform

Opens extensions.blender.org < https://extensions.blender.org/> in a web browser.

Refresh Remote

Manually check the online repositories for available updates.

Refresh Local

Scan extension & legacy add-ons for changes to modules & meta-data (similar to restarting). Any issues are reported as warnings

Install Available Updates

Update all the extensions that have an update available.

Install from Disk

Install an extension from a . zip package. This is installed to a Local Repository and no updates will be available.

This can also be used to install legacy Add-ons, for more information see: Installing Legacy Add-ons.

Filter by Type

Or show only extensions of a single type:

Add-ons:

Only show add-ons.


Themes:

Only show themes.

Repositories

By default Blender has a Remote Repository pointing towards the Official Blender Extensions Platform and two Local Repositories.

In the cases where more repositories are needed (e.g., to access third party extension platforms), new repositories can be added.



Repositories.

To add new repositories click on the + icon:

Add Remote Repository

Add a repository from a URL.

Add Local Repository

Add a repository which will be managed by the user (to be used with Install from Disk).

To remove repositories click on the - icon:

Remove Repository

Remove an extension repository.

Remove Repository & Files

Remove a repository and delete all associated files when removing.

These changes are permanent and cannot be reversed.

Remote Repository

Remote repository with support for listing and updating extensions.

Options:

Check for Updates on Startup

Allows Blender to check for updates upon launch. When updates are available a notification will be visible on the status bar.

Access Token

Personal access token, may be required by some repositories.

Local Repository

A repository managed manually by the users.

There are two types of local repositories. By default new local repositories are added as User repositories. This is what you want most of the time.

After creating a repository they can be changed in the Advanced options to have a source System. These repositories are intended to bundle extensions with Blender, to make it portable.

Previous Animation Copyright ${\mathbb C}$: This page is licensed under a CC-BY-SA 4.0 Int. License Made with Furo

Last updated on 2025-05-10

No

Add-c

View Source View Translation Report issue on this page