软件使用说明文档

实现的功能


默认连接使用网易 163SMTP 服务器进行邮件发送

操作步骤

```
D:\pythonProject\venv\Scripts\python.exe D:/pythonProject/Client.py
Please input your mailaddress:oym8716494940163.com
```

首先输入自己的 163 邮箱地址 (作为登录用户名的同时也作为发送邮箱)

接着输入自己的 163 邮箱授权密码



接着是收件邮箱地址

```
D:\pythonProject\venv\Scripts\python.exe D:/pythonProject/Client.py
Please input your mailaddress: pythonProject/Client.py
Please input your mailaddress Authorization password:
Please input the mailaddress you want to send to:pythonProject/Client.py
Please input the mailaddress you want to send to:pythonProject/Client.py
Please input the mailaddress you want to send to:pythonProject/Client.py
Please input your mailaddress Authorization password:
Please input tyour subject:Stip Ball Client Testing
Please input your subject:Stip Ball Client Testing
Please input your subject:Stip Ball Client Testing
```

提示信息显示后输入待发送邮件标题

```
Client X

D:\pythonProject\venv\Scripts\python.exe D:/pythonProject/Client.py
Please input your mailaddress: nationActivation
Please input your mailaddress Authorization password: IEVENUESCRIPTS
Please input the mailaddress you want to send to: nationActivation
Server message after connection request: 220 163.com Anti-spam GT for Coremail System (163com[20141201])

Server response after HELO: 250 0K

Server response after AUTH LOGIN: 334 dXNlcm5hbWU6

Server response after sending username: 334 UGFzc3dvcmQ6

Server response after sending password: 235 Authentication successful

Server response After MAIL FROM command: 250 Mail OK

Server response After RCPT TO command: 250 Mail OK

Server response After DATA command: 354 End data with <CR><LF>.<CR><LF>
Please input your subject: SHTP Noil Client Testing

Please enter your message: This is a message using setp mail client
```

输入邮件内容

最后发送成功并显示提示信息



This is a message using smtp mail client

收件箱收到邮件