
1
ServoStartUpTimer
EC1.I_EC1_RTO_SD1
TON
IN
PT
T#10s
Q
ET
ServoEnable
EC1.Q_EnableServo
2
Servo Motor Power/Enable
mcPower
MC_Power
MAIN.myAxis
Axis
Status
Busy
Active
Error
ErrorID
ServoEnable
Enable
ServoEnable
Enable_Positive
ServoEnable
Enable_Negative
Override
BufferMode
Options

3 *Move Carrage to given position - (Inverse the given position)*




4
MoveCarrage to given position
MC_MoveAbsolute
MC_MoveAbsolute
MAIN.myAxis
Axis
Done
Busy
Active
CommandAborted
Error
ErrorID
ExecMABS
LE
EN
≤
Abs_Pos
82200
GE
EN
≥
Abs_Pos
0
Execute
MAIN.bServoMove
PositionInv
Position
velocity
Velocity
100
Acceleration
Deceleration
Jerk
BufferMode
Options


5
Carrage Jog Fwd/Rvs
MC_Jog
MC_Jog
MAIN.myAxis
Axis
Done
Busy
Active
CommandAborted
Error
ErrorID
CarrageAtFront
JogRvs
JogForward
common.CarrageHomingRvs
CarrageMoveToStartPos
CarrageAtEnd
JogFwd
JogBackwards
common.CarrageHomingFwd
Mode
Position


velocity
Velocity
100
Acceleration
Deceleration
Jerk
6
???
MC_Cal_Jog
MC_Jog
MAIN.myAxis
Axis
Done
Busy
CarrageCalPos
CalJog
Active
JogForward
CommandAborted
Error
ErrorID
Mode
Position
velocity
Velocity
100
Acceleration
Deceleration
Jerk

7 *Servo reset function*



8 *Servo motor stop - Activated from ServoStop signal from HMI or stop pulse generated when carrage reach to min or max.*



9 *Check Limit Sensors*



10



11



12 *Read Servo position*



13 *Inverse read servo position*



14 *Generate 500ms pulse to Servo Stop function when carrage reach to min and max positions*



15 *When Carrage reach to front generate pulse to MC_Home function to set position to 0.*



16 *Set position 0 as Servo Home function*



17