helm create haproxy-controller-devops

```
[mostafa@hostname helm]$ helm install haproxy-devops ./haproxy-controller-devops --create-namespace
 --namespace haproxy-controller-devops
NAME: haproxy-devops
LAST DEPLOYED: Mon Apr 28 12:11:41 2025
NAMESPACE: haproxy-controller-devops
STATUS: deployed
REVISION: 1
NOTES:
1. Get the application URL by running these commands:
  export POD_NAME=$(kubectl get pods --namespace haproxy-controller-devops -l "app.kubernetes.io/na
me=haproxy-controller-devops,app.kubernetes.io/instance=haproxy-devops" -o jsonpath="{.items[0].met
adata.name}")
  export CONTAINER_PORT=$(kubectl get pod --namespace haproxy-controller-devops $POD_NAME -o jsonpa
th="{.spec.containers[0].ports[0].containerPort}")
  echo "Visit http://127.0.0.1:8080 to use your application"
  kubectl --namespace haproxy-controller-devops port-forward $POD_NAME 8080:$CONTAINER_PORT
[mostafa@hostname helm]$
```

mostafa@hostname:~/Desktop/helm

```
[mostafa@hostname helm]$ helm list -A
NAME                 NAMESPACE                        REVISION        UPDATED
        STATUS      CHART                            APP VERSION
haproxy-devops  haproxy-controller-devops        1               2025-04-28 12:11:41.133854766 +0300
  EEST    deployed         haproxy-controller-devops-0.1.0 1.16.0
```

Not secure 192.168.49.2:32678

(DevSecOps-N... | ChatGPT | QuickRefME | Python3 Bootc... | Docs | DXC Technolo... | G |

HAProxy version 3.0.10-346eb4f, released 2025/04/22
Statistics Report for pid 124

> General process information

pid = 124 (process #1, nbproc = 1, nbthread = 4)
uptime = 0d 0h37m19s; warnings = 0
system limits: memmax = 2581 MB; ulimit-n = 148113
maxsock = 148113; maxconn = 74000; reached = 0; maxpipes = 0
current conns = 1; current pipes = 0/0; conn rate = 1/sec; bit rate = 118.825 kbps
Running tasks: 0/67 (0 niced); idle = 100 %

	active UP	backup UP
	active UP, going down	backup UP, going down
	active DOWN, going up	backup DOWN, going up
	active or backup DOWN	not checked
	active or backup DOWN for maintenance (MAINT)	
	active or backup SOFT STOPPED for maintenance	

Note: "NOLB"/"DRAIN" = UP with load-balancing disabled.

Display option:
- Scope :
- Hide 'DOWN' servers
- Disable refresh
- Refresh now
- CSV export
- JSON export (schema)

External resources:
- Primary site
- Updates (v3.0)
- Online manual