

Ejercicio 2 parcial 02- RDC

Carnet: 00018824; A: 12; B: 99; Julio Alejandro Flores Diaz

Red: 192.12.99.0/24

```
Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Meng (mirnshi@gmail.com)
All rights reserved.

VPSS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

PC1> enable
Bad command: "enable". Use ? for help.

PC1> ip 192.12.99.2 255.255.255.192 192.12.99.1
Checking for duplicate address...
save
show ip
PC1 : 192.12.99.2 255.255.255.192 gateway 192.12.99.1

PC1> save
Saving startup configuration to startup.vpc
. done

PC1> show ip

NAME       : PC1[1]
IP/MASK    : 192.12.99.2/26
GATEWAY    : 192.12.99.1
DNS        :
MAC        : 00:50:79:66:68:00
LPORT      : 10060
RHOST:PORT : 127.0.0.1:10061
MTU        : 1500

PC1> trace 192.12.99.130
trace to 192.12.99.130, 8 hops max, press Ctrl+C to stop
 1 192.12.99.1  15.648 ms 15.423 ms 15.030 ms
 2 192.12.99.153 45.671 ms 46.818 ms 45.575 ms
 3 **192.12.99.130 60.604 ms (ICMP type:3, code:3, Destination port unreachable)

PC1>
```

```
Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Meng (mirnshi@gmail.com)
All rights reserved.

VPSS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

PC2> ip 192.12.99.66 255.255.255.224 192.12.99.65
Checking for duplicate address...
save
show ip
PC1 : 192.12.99.66 255.255.255.224 gateway 192.12.99.65

PC2> save
Saving startup configuration to startup.vpc
. done

PC2> show ip

NAME       : PC2[1]
IP/MASK    : 192.12.99.66/27
GATEWAY    : 192.12.99.65
DNS        :
MAC        : 00:50:79:66:68:01
LPORT      : 10059
RHOST:PORT : 127.0.0.1:10059
MTU        : 1500

PC2> ping 192.12.99.98
192.12.99.98 icmp_seq=1 timeout
84 bytes from 192.12.99.98 icmp_seq=2 ttl=62 time=60.872 ms
84 bytes from 192.12.99.98 icmp_seq=3 ttl=62 time=61.714 ms
84 bytes from 192.12.99.98 icmp_seq=4 ttl=62 time=61.661 ms
84 bytes from 192.12.99.98 icmp_seq=5 ttl=62 time=60.726 ms

PC2>
```

PC1PC2PC3PC4PC5R1R2R3R4R5FPS N/AGPU 0%CPU 7%RAM N/A

Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Peng (mirnshi@gmail.com)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

PC3> ip 192.12.99.98 255.255.255.240 192.12.99.97
Checking for duplicate address...
save
show PC1 : 192.12.99.98 255.255.255.240 gateway 192.12.99.97

PC3> save
Saving startup configuration to startup.vpc
.: done

PC3> show ip

NAME : PC3[1]
IP/MASK : 192.12.99.98/28
GATEWAY : 192.12.99.97
DNS :
MAC : 00:50:79:66:68:02
LPORT : 10056
RHOST:PORT : 127.0.0.1:10057
MTU : 1500

PC3> trace 192.12.99.114
trace to 192.12.99.114, 8 hops max, press Ctrl+C to stop
1 192.12.99.97 15.654 ms 15.186 ms 16.198 ms
2 192.12.99.141 45.698 ms 45.357 ms 46.078 ms
3 **192.12.99.114 60.815 ms (ICMP type:3, code:3, Destination port unreachable)

PC3>

solarwinds Solar-PuTTY free tool © 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.

28°C
Parc soleado

Buscar

ENG 80% 12:08
5/6/2026

PC1PC2PC3PC4PC5R1R2R3R4R5FPS N/AGPU 0%CPU 7%RAM N/A

Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Peng (mirnshi@gmail.com)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

PC4> ip 192.12.99.114 255.255.255.240 192.12.99.113
Checking for duplicate address...
save
show PC1 : 192.12.99.114 255.255.255.240 gateway 192.12.99.113

PC4> save
Saving startup configuration to startup.vpc
.: done

PC4> show ip

NAME : PC4[1]
IP/MASK : 192.12.99.114/28
GATEWAY : 192.12.99.113
DNS :
MAC : 00:50:79:66:68:03
LPORT : 10062
RHOST:PORT : 127.0.0.1:10063
MTU : 1500

PC4> ping 192.12.99.130
84 bytes from 192.12.99.130 icmp_seq=1 ttl=61 time=92.224 ms
84 bytes from 192.12.99.130 icmp_seq=2 ttl=61 time=91.294 ms
84 bytes from 192.12.99.130 icmp_seq=3 ttl=61 time=90.637 ms
84 bytes from 192.12.99.130 icmp_seq=4 ttl=61 time=91.008 ms
84 bytes from 192.12.99.130 icmp_seq=5 ttl=61 time=90.521 ms

PC4>

solarwinds Solar-PuTTY free tool © 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.

28°C
Parc soleado

Buscar

ENG 80% 12:08
5/6/2026

PC1PC2PC3PC4PC5R1R2R3R4R5FPS N/A GPU CPU 80% NAT

Welcome to Virtual PC Simulator, version 0.6.2
Dedicated to Daling.
Build time: Apr 10 2019 02:42:20
Copyright (c) 2007-2014, Paul Meng (mirnshi@gmail.com)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.

Press '?' to get help.

Executing the startup file

PC5> ip 192.12.99.130 255.255.255.248 192.12.99.129
Checking for duplicate address...
save
show ip
PC1 : 192.12.99.130 255.255.255.248 gateway 192.12.99.129

PC5> save
Saving startup configuration to startup.vpc
- done

PC5> show ip

NAME : PC5[1]
IP/MASK : 192.12.99.130/20
GATEWAY : 192.12.99.129
DNS :
MAC : 00:50:79:66:68:04
LPORT : 10064
RHOST:PORT : 127.0.0.1:10065
MTU : 1500

PC5> trace 192.12.99.66
trace to 192.12.99.66, 8 hops max, press Ctrl+C to stop
1 192.12.99.129 15.729 ms 15.419 ms 15.197 ms
2 192.12.99.154 47.227 ms 45.617 ms 45.252 ms
3 192.12.99.157 76.412 ms 76.094 ms 75.541 ms
4 *192.12.99.66 90.537 ms (ICMP type:3, code:3, Destination port unreachable)

PC5>

solarwinds Solar-PuTTY free tool © 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.

28°C Parc soleado Buscar 12:08 5/6/2026

PC1PC2PC3PC4PC5R1R2R3R4R5FPS N/A GPU CPU 80% NAT

*Mar 1 00:16:15.711: %OSPF-5-ADJCHG: Process 1, Nbr 192.12.99.149 on Serial2/1 from LOADING to FULL, Loading Done
R1#network 192.12.99.136 0.0.0.3 area 0
^
% Invalid input detected at '^' marker.

R1#
Building configuration...
[OK]
R1#show ip inter
R1#show ip interface br
R1#show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
FastEthernet0/0	192.12.99.113	YES	manual	up	up
FastEthernet0/1	unassigned	YES	unset	administratively down	down
FastEthernet1/0	unassigned	YES	unset	administratively down	down
Serial1/0	192.12.99.137	YES	manual	up	up
Serial2/1	192.12.99.141	YES	manual	up	up
Serial2/2	unassigned	YES	unset	administratively down	down
Serial2/3	unassigned	YES	unset	administratively down	down

R1#show ip rou
R1#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODM, P - periodic downloaded static route

Gateway of last resort is not set

192.12.99.0/24 is variably subnetted, 11 subnets, 5 masks
C 192.12.99.140/30 is directly connected, Serial2/1
C 192.12.99.136/30 is directly connected, Serial2/0
O 192.12.99.128/29 [110/75] via 192.12.99.142, 00:02:23, Serial2/1
O 192.12.99.156/30 [110/65] via 192.12.99.138, 00:05:22, Serial2/0
O 192.12.99.152/30 [110/75] via 192.12.99.142, 00:02:33, Serial2/1
O 192.12.99.148/30 [110/75] via 192.12.99.138, 00:00:55, Serial2/0
O 192.12.99.148/30 [110/65] via 192.12.99.142, 00:04:16, Serial2/1
O 192.12.99.144/30 [110/74] via 192.12.99.142, 00:04:26, Serial2/1
O 192.12.99.144/30 [110/74] via 192.12.99.138, 00:06:03, Serial2/0
O 192.12.99.0/26 [110/75] via 192.12.99.138, 00:00:57, Serial2/0
O 192.12.99.96/28 [110/74] via 192.12.99.142, 00:03:53, Serial2/1
C 192.12.99.112/28 is directly connected, FastEthernet0/0
O 192.12.99.64/27 [110/74] via 192.12.99.138, 00:08:40, Serial2/0

R1#

solarwinds Solar-PuTTY free tool © 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.

28°C Parc soleado Buscar 12:08 5/6/2026

PC1PC2PC3PC4PC5R1R2R3R4R5FPS N/A CPU 11% AT N/A

```
R2#
Building configuration...
[OK]
R2#
*Mar 1 00:14:55.391: %SYS-5-CONFIG_I: Configured from console by console
R2#
*Mar 1 00:15:49.595: %OSPF-5-ADJCHG: Process 1, Nbr 192.12.99.149 on FastEthernet0/1 from LOADING to FULL, Loading Done
R2#
*Mar 1 00:19:11.163: %OSPF-5-ADJCHG: Process 1, Nbr 192.12.99.158 on FastEthernet1/0 from LOADING to FULL, Loading Done
R2#show ip inter
R2#show ip interface br
R2#show ip interface brief
Interface          IP-Address      OK? Method Status      Protocol
FastEthernet0/0    192.12.99.65    YES manual up          up
FastEthernet0/1    192.12.99.145  YES manual up          up
FastEthernet1/0    192.12.99.157  YES manual up          up
Serial2/0          192.12.99.138  YES manual up          up
Serial2/1          unassigned     YES unset  administratively down down
Serial2/2          unassigned     YES unset  administratively down down
Serial2/3          unassigned     YES unset  administratively down down
R2#show ip rou
R2#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2
        I - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
        ia - IS-IS inter area, * - candidate default, U - per-user static route
        o - OOR, P - periodic downloaded static route

Gateway of last resort is not set

192.12.99.0/24 is variably subnetted, 11 subnets, 5 masks
O    192.12.99.140/30 [110/74] via 192.12.99.146, 00:04:08, FastEthernet0/1
C    192.12.99.136/30 is directly connected, Serial2/0
O    192.12.99.128/29 [110/21] via 192.12.99.150, 00:00:39, FastEthernet1/0
        [110/21] via 192.12.99.146, 00:02:07, FastEthernet0/1
C    192.12.99.156/30 is directly connected, FastEthernet1/0
O    192.12.99.152/30 [110/11] via 192.12.99.158, 00:00:39, FastEthernet1/0
O    192.12.99.148/30 [110/11] via 192.12.99.146, 00:04:00, FastEthernet0/1
C    192.12.99.144/30 is directly connected, FastEthernet0/1
O    192.12.99.0/26 [110/11] via 192.12.99.150, 00:00:51, FastEthernet1/0
O    192.12.99.96/28 [110/20] via 192.12.99.146, 00:03:37, FastEthernet0/1
O    192.12.99.112/28 [110/74] via 192.12.99.137, 00:06:03, Serial2/0
C    192.12.99.64/27 is directly connected, FastEthernet0/0
R2#
```

solarwinds Solar-PuTTY free tool © 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.

28°C Parc soleado

Buscar

80% 12:08 5/6/2026

PC1PC2PC3PC4PC5R1R2R3R4R5FPS N/A CPU 11% AT N/A

```
R3(config-router)#network 192.12.99.96 0.0.0.15 area 0
R3(config-router)#end
R3#
Building configuration...
[OK]
R3#
*Mar 1 00:15:00.259: %SYS-5-CONFIG_I: Configured from console by console
R3#
*Mar 1 00:16:12.767: %OSPF-5-ADJCHG: Process 1, Nbr 192.12.99.153 on FastEthernet1/0 from LOADING to FULL, Loading Done
R3#show ip inter
R3#show ip interface br
R3#show ip interface brief
Interface          IP-Address      OK? Method Status      Protocol
FastEthernet0/0    192.12.99.97    YES manual up          up
FastEthernet0/1    192.12.99.146  YES manual up          up
FastEthernet1/0    192.12.99.149  YES manual up          up
Serial2/0          unassigned     YES unset  administratively down down
Serial2/1          192.12.99.142  YES manual up          up
Serial2/2          unassigned     YES unset  administratively down down
Serial2/3          unassigned     YES unset  administratively down down
R3#show ip rou
R3#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2
        I - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
        ia - IS-IS inter area, * - candidate default, U - per-user static route
        o - OOR, P - periodic downloaded static route

Gateway of last resort is not set

192.12.99.0/24 is variably subnetted, 11 subnets, 5 masks
C    192.12.99.140/30 is directly connected, Serial2/1
O    192.12.99.136/30 [110/74] via 192.12.99.145, 00:04:00, FastEthernet0/1
O    192.12.99.128/29 [110/11] via 192.12.99.150, 00:01:58, FastEthernet1/0
O    192.12.99.156/30 [110/11] via 192.12.99.145, 00:04:00, FastEthernet0/1
O    192.12.99.152/30 [110/11] via 192.12.99.150, 00:02:00, FastEthernet1/0
C    192.12.99.148/30 is directly connected, FastEthernet1/0
C    192.12.99.144/30 is directly connected, FastEthernet0/1
O    192.12.99.0/26 [110/21] via 192.12.99.150, 00:00:32, FastEthernet1/0
        [110/21] via 192.12.99.145, 00:00:32, FastEthernet0/1
C    192.12.99.96/28 is directly connected, FastEthernet0/0
O    192.12.99.112/28 [110/74] via 192.12.99.141, 00:04:27, Serial2/1
O    192.12.99.64/27 [110/20] via 192.12.99.145, 00:04:01, FastEthernet0/1
R3#
```

solarwinds Solar-PuTTY free tool © 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.

28°C Parc soleado

Buscar

80% 12:09 5/6/2026

PC1PC2PC3PC4PC5R1R2R3R4R5FPS N/A | CPU 100% | RAM N/A

```
R4#show ip interface brief
Interface IP-Address OK? Method Status Protocol
FastEthernet0/0 192.12.99.129 YES manual up up
FastEthernet0/1 192.12.99.153 YES manual up up
FastEthernet1/0 192.12.99.150 YES manual up up
Serial12/0 unassigned YES unset administratively down down
Serial12/1 unassigned YES unset administratively down down
Serial12/2 unassigned YES unset administratively down down
Serial12/3 unassigned YES unset administratively down down

R4#show ip rou
R4#show ip interface brief
Interface IP-Address OK? Method Status Protocol
FastEthernet0/0 192.12.99.129 YES manual up up
FastEthernet0/1 192.12.99.153 YES manual up up
FastEthernet1/0 192.12.99.150 YES manual up up
Serial12/0 unassigned YES unset administratively down down
Serial12/1 unassigned YES unset administratively down down
Serial12/2 unassigned YES unset administratively down down
Serial12/3 unassigned YES unset administratively down down

R4#show ip rou
R4#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2
        i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
        ia - IS-IS inter area, * - candidate default, U - per-user static route
        o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

192.12.99.0/24 is variably subnetted, 11 subnets, 5 masks
O 192.12.99.148/30 [110/65] via 192.12.99.149, 00:02:05, FastEthernet1/0
O 192.12.99.136/30 [110/75] via 192.12.99.154, 00:00:20, FastEthernet0/1
O 192.12.99.128/29 [110/75] via 192.12.99.149, 00:02:05, FastEthernet1/0
C 192.12.99.128/29 is directly connected, FastEthernet0/0
O 192.12.99.156/30 [110/11] via 192.12.99.154, 00:00:20, FastEthernet0/1
C 192.12.99.152/30 is directly connected, FastEthernet0/1
C 192.12.99.148/30 is directly connected, FastEthernet1/0
O 192.12.99.144/30 [110/11] via 192.12.99.149, 00:02:07, FastEthernet1/0
O 192.12.99.0/26 [110/20] via 192.12.99.154, 00:00:22, FastEthernet0/1
O 192.12.99.96/28 [110/11] via 192.12.99.149, 00:02:07, FastEthernet1/0
O 192.12.99.112/28 [110/75] via 192.12.99.149, 00:02:07, FastEthernet1/0
O 192.12.99.64/27 [110/21] via 192.12.99.154, 00:00:22, FastEthernet0/1
O 192.12.99.64/27 [110/21] via 192.12.99.149, 00:02:07, FastEthernet1/0
```

solarwinds Solar-PuTTY free tool © 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.

28°C Parc soleado 12:09 5/6/2026

PC1PC2PC3PC4PC5R1R2R3R4R5FPS N/A | CPU 100% | RAM N/A

```
R5(config-router)#end
R5#
Building configuration...
[OK]
R5#
*Mar 1 00:15:17.947: %SYS-5-CONFIG_I: Configured from console by console

R5#show ip in
Mar 1 00:15:24.991: %OSPF-5-ADJCHG: Process 1, Nbr 192.12.99.153 on FastEthernet0/1 from LOADING to FULL, Loading Done

R5#show ip inte
R5#show ip interface br
R5#show ip interface brief
Interface IP-Address OK? Method Status Protocol
FastEthernet0/0 192.12.99.1 YES manual up up
FastEthernet0/1 192.12.99.154 YES manual up up
FastEthernet1/0 192.12.99.158 YES manual up up
Serial12/0 unassigned YES unset administratively down down
Serial12/1 unassigned YES unset administratively down down
Serial12/2 unassigned YES unset administratively down down
Serial12/3 unassigned YES unset administratively down down

R5#show ip rou
R5#show ip route
Codes: C - connected, S - static, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2
        i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
        ia - IS-IS inter area, * - candidate default, U - per-user static route
        o - ODR, P - periodic downloaded static route

Gateway of last resort is not set

192.12.99.0/24 is variably subnetted, 11 subnets, 5 masks
O 192.12.99.140/30 [110/75] via 192.12.99.157, 00:00:13, FastEthernet1/0
O 192.12.99.136/30 [110/65] via 192.12.99.157, 00:00:03, FastEthernet0/1
O 192.12.99.128/29 [110/20] via 192.12.99.153, 00:00:03, FastEthernet1/0
C 192.12.99.156/30 is directly connected, FastEthernet1/0
C 192.12.99.152/30 is directly connected, FastEthernet0/1
O 192.12.99.148/30 [110/11] via 192.12.99.153, 00:00:05, FastEthernet0/1
O 192.12.99.144/30 [110/11] via 192.12.99.157, 00:00:15, FastEthernet1/0
C 192.12.99.0/26 is directly connected, FastEthernet0/0
O 192.12.99.96/28 [110/21] via 192.12.99.157, 00:00:15, FastEthernet1/0
O 192.12.99.112/28 [110/21] via 192.12.99.153, 00:00:05, FastEthernet0/1
O 192.12.99.112/28 [110/75] via 192.12.99.157, 00:00:15, FastEthernet1/0
O 192.12.99.64/27 [110/11] via 192.12.99.157, 00:04:12, FastEthernet1/0
```

solarwinds Solar-PuTTY free tool © 2019-2024 SolarWinds Worldwide, LLC. All rights reserved.

28°C Parc soleado 12:09 5/6/2026

126=...192 } 127=...224 } 128=...240

129=...248 } 130=...252

DISP	Interface	IP	mask	gateway	wildmask
✓ R1	Fe 0/0 - P04	192.12.99.113	128	NA	0.0.0.15
✓ R1	Serial 2/0 - R2	192.12.99.137	130	NA	0.0.0.3
✓ R1	Serial 2/1 - R3	192.12.99.141	130	NA	0.0.0.3
✓ R2	Serial 2/0 - R1	192.12.99.138	130	NA	0.0.0.3
✓ R2	Fe 0/0 - P02	192.12.99.65	127	NA	0.0.0.31
✓ R2	Fe 0/1 - R3	192.12.99.145	130	NA	0.0.0.3
✓ R2	Fe 1/0 - R5	192.12.99.157	130	NA	0.0.0.3
R3	Serial 2/1 - R1	192.12.99.142	130	NA	0.0.0.3
R3	Fe 0/0 - P03	192.12.99.97	128	NA	0.0.0.15
R3	Fe 0/1 - R2	192.12.99.146	130	NA	0.0.0.3
R3	Fe 1/0 - R4	192.12.99.149	130	NA	0.0.0.3
R4	Fe 0/0 - P05	192.12.99.129	129	NA	0.0.0.7
R4	Fe 0/1 - R5	192.12.99.153	130	NA	0.0.0.3
R4	Fe 1/0 - R3	192.12.99.150	130	NA	0.0.0.3
R5	Fe 0/0 - P01	192.12.99.1	126	NA	0.0.0.63
R5	Fe 0/1 - R4	192.12.99.154	130	NA	0.0.0.3
R5	Fe 1/0 - R2	192.12.99.158	130	NA	0.0.0.3
P01	Holo - R5	192.12.99.2	126	192.12.99.1	0.0.0.63
P02	Holo - R2	192.12.99.66	127	192.12.99.65	0.0.0.31
P03	Holo - R3	192.12.99.98	128	192.12.99.97	0.0.0.15
P04	Holo - R1	192.12.99.114	128	192.12.99.113	0.0.0.15
P05	Holo - R4	192.12.99.130	129	192.12.99.129	0.0.0.7