

type filter text

- Resource
 - General**
 - Build
- MSP430 Compiler
 - Processor Options
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - Advanced Options
 - MSP430 Linker
 - MSP430 Hex Utility [Disabled]
 - Debug

General

Configuration: Debug [Active] Manage Configurations...

Project Products MPU

Device

Family: MSP430

Variant: <select or type filter text> MSP430FR5729

Connection: TI MSP430 USB1 [Default] Identify...

☒ Manage the project's target-configuration automatically

Project type and tool-chain

Compiler version: TI v21.6.1.LTS More...

Output type: Executable

Output format: eabi (ELF)

Device endianness: little

Linker command file: lnk_msp430fr5729.cmd Browse...

Runtime support library: Browse...

[Show advanced settings](#)

Apply and Close

Cancel

type filter text

- Resource
 - General**
 - Build
- ▼ Build
 - ▼ MSP430 Compiler
 - Processor Options
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
 - > MSP430 Linker
 - MSP430 Hex Utility [Disabled]
 - > Debug

General

Configuration: Debug [Active]

Manage Configurations...

Project Products MPU

☐ Enable Memory Protection Unit (MPU)

- ☒ Let compiler handle memory partitioning, associated access rights, and linker output section placement
- ☐ Manually specify memory segment boundaries and access rights

0xFF7F	Segment 3	R W X	☒ ☐ ☒	☒ Assert PUC on access rights violation
0xC600	Segment 2	R W X	☒ ☐ ☐	☒ Assert PUC on access rights violation
0xC400	Segment 1	R W X	☒ ☒ ☐	☒ Assert PUC on access rights violation
0xC200	Info Memory	R W X	☒ ☐ ☐	☒ Assert PUC on access rights violation

? [Show advanced settings](#)

Apply and Close

Cancel

type filter text

- > Resource
 - General
- > Build
 - > MSP430 Compiler
 - Processor Options**
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
- > MSP430 Linker
 - MSP430 Hex Utility [Disabled]
- > Debug

Processor Options

Configuration: Debug [Active] Manage Configurations...

Silicon version (--silicon_version, -v) mbsp

Specify the code memory model (--code_model) small

Specify the data memory model (--data_model) small

Indicates what data must be near (--near_data) globals

[Show advanced settings](#)

Apply and Close

Cancel

type filter text

- > Resource
 - General
- > Build
 - > MSP430 Compiler
 - Processor Options
 - Optimization**
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
- > MSP430 Linker
 - MSP430 Hex Utility [Disabled]
- > Debug

Optimization

Configuration: Debug [Active]

Manage Configurations...

Optimization level (--opt_level, -O)

4 - Whole Program Optimizations

Speed vs. size trade-offs (--opt_for_speed, -mf)

0

0 (size)

5 (speed)

☐ Align functions and loops for power (--align_for_power)

Inline hardware multiply version of RTS mpy routine (--use_hw_mpy)

F5

? [Show advanced settings](#)

Apply and Close

Cancel

type filter text

- > Resource
 - General
- > Build
 - > MSP430 Compiler
 - Processor Options
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
 - Advanced Debug Options
 - Language Options**
 - Parser Preprocessing Options
 - Diagnostic Options
 - Runtime Model Options
 - Advanced Optimizations
 - Entry/Exit Hook Options
 - Feedback and Analysis Options
 - Library Function Assumptions
 - Assembler Options
 - File Type Specifier
 - Directory Specifier
 - Default File Extensions
 - Command Files

Language Options

Configuration: Debug [Active] Manage Configurations...

C Dialect Compile program in C99 mode (--c99)

C++ Dialect Compile program in C++14 mode (--c++14)

Language mode Relaxed parsing (non-strict ANSI) (--relaxed_ansi, -pr)

☐ Enable C++ exception handling (--exceptions)

☐ Support C++ run-time type information (--rtti, -rtti)

☐ Treat C files as C++ files (--cpp_default, -fg)

☐ Allow extern C functions to propagate exceptions (--extern_c_can_throw)

Floating point precision accepted by compiler (--float_operations_allowed) none

Specify how to treat plain chars (signed/unsigned) (--plain_char) unsigned

Limit pending template instantiations (--pending_instantiations)

Level of printf/scanf support required (--printf_support) minimal

type filter text

- > Resource
 - General
- > Build
 - > MSP430 Compiler
 - Processor Options
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
 - Advanced Debug Options
 - Language Options
 - Parser Preprocessing Options
 - D diagnostic Options
 - Runtime Model Options**
 - Advanced Optimizations
 - Entry/Exit Hook Options
 - Feedback and Analysis Options
 - Library Function Assumptions
 - Assembler Options
 - File Type Specifier
 - Directory Specifier
 - Default File Extensions
 - Command Files

① --small_enum is deprecated and will be removed in a subsequent release. Use --enum_type=packed instead.

Configuration: Debug [Active]

Manage Configurations...

Place structs and arrays in separate subsections (--gen_data_subsections)

on

Designate enum type (--enum_type)

packed

Use ELF common symbols (--common)

① on

☐ Reserve a register for use by the user (--global_register) [r4]

☐ Reserve a register for use by the user (--global_register) [r5]

☐ Use large-data memory model (--large_memory_model, -ml)

Run functions from RAM (--ramfunc)

☐ Workaround specified silicon errata (--silicon_errata) [CPU12]

☐ Workaround specified silicon errata (--silicon_errata) [CPU13]

☐ Workaround specified silicon errata (--silicon_errata) [CPU15]

☐ Workaround specified silicon errata (--silicon_errata) [CPU18]

☐ Workaround specified silicon errata (--silicon_errata) [CPU19]

☒ Workaround specified silicon errata (--silicon_errata) [CPU21]

☒ Workaround specified silicon errata (--silicon_errata) [CPU22]

☐ Workaround specified silicon errata (--silicon_errata) [CPU23]

☒ Workaround specified silicon errata (--silicon_errata) [CPU40]

☒ Enums may be char/short, instead of int (--small_enum, --small-enum) [deprecated] ①

① [Show advanced settings](#)

Apply and Close

Cancel

type filter text

- > Resource
 - General
- > Build
 - > MSP430 Compiler
 - Processor Options
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
 - Advanced Debug Options
 - Language Options
 - Parser Preprocessing Options
 - Dagnostic Options
 - Runtime Model Options
 - Advanced Optimizations**
 - Entry/Exit Hook Options
 - Feedback and Analysis Options
 - Library Function Assumptions
 - Assembler Options
 - File Type Specifier
 - Directory Specifier
 - Default File Extensions
 - Command Files

Advanced Optimizations

Configuration: Debug [Active] Manage Configurations...

Allow reassociation of FP arithmetic (--fp_reassoc) off

Allow reassociation of sat arithmetic (--sat_reassoc) off

☐ Program mode compilation (--program_level_compile, -pm)

Specify call assumptions when optimizing (--call_assumptions, -op) 3

Specify threshold for automatic inlining (--auto_inline, -oi) 100

☐ Disable inlining (--disable_inlining)

Inline hardware multiply version of RTS mpy routine (--disable_interrupts_around_hw_mpy)

☐ Assume called funcs create hidden aliases (rare) (--aliased_variables, -ma)

type filter text

- > Resource
 - General
- > Build
 - > MSP430 Compiler
 - Processor Options
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
 - > MSP430 Linker
 - Basic Options**
 - File Search Path
 - > Advanced Options
 - MSP430 Hex Utility [Disabled]
- > Debug

Basic Options

Configuration: Debug [Active] Manage Configurations...

Specify the output path for section dependence information (--emit_references:file)

☐ Specify the format for section reference information (--emit_references:format) [TEXT]

Link information (map) listed into <file> (--map_file, -m)

Specify output file name (--output_file, -o)

Heap size for C/C++ dynamic memory allocation (--heap_size, -heap)

Set C system stack size (--stack_size, -stack)

Hold watchdog timer during cinit auto-initialization (--cinit_hold_wdt) off

[Show advanced settings](#)

Apply and Close

Cancel

type filter text

- > Resource
 - General
- > Build
 - MSP430 Compiler
 - Processor Options
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
 - MSP430 Linker
 - Basic Options
 - File Search Path
 - Advanced Options
 - Command File Preprocessing
 - Diagnostics
 - Linker Output
 - Symbol Management
 - Runtime Environment**
 - Miscellaneous
 - MSP430 Hex Utility [Disabled]
- > Debug

Runtime Environment

Configuration: Debug [Active]

Manage Configurations...

Set C argc/argv memory size (--arg_size, --args)

0

Compress ELF C style auto initialization data (--cinit_compression)

off

Compress ELF sections copied using copy tables (--copy_compression)

off

Default fill value for holes in output sections (--fill_value, -f)

Initialization model

Link using ROM autoinitialization model (--rom_model, -c)

? [Show advanced settings](#)

Apply and Close

Cancel

type filter text

- > Resource
 - General
- > Build
 - > MSP430 Compiler
 - Processor Options
 - Optimization
 - Include Options
 - ULP Advisor
 - Advice Options
 - Predefined Symbols
 - > Advanced Options
 - > MSP430 Linker
 - Basic Options
 - File Search Path
 - > Advanced Options
 - Command File Preprocessing
 - Diagnostics
 - Linker Output
 - Symbol Management
 - Runtime Environment
 - Miscellaneous**
 - MSP430 Hex Utility [Disabled]
- > Debug

Miscellaneous

Configuration: Debug [Active]

Manage Configurations...

Aggressively reduce size of the DWARF information (--compress_dwarf)

☐ Disable conditional linking and ignore .clink (--disable_clink, -j)

Add <function> to preferred placement order list (--preferred_order)



Eliminate sections not needed in the executable (--unused_section_elimination)

on

Zero initialize ELF uninitialized sections (--zero_init)

off

? [Show advanced settings](#)

Apply and Close

Cancel