LLARS - Getting Started & Script Setup Guide

LLARS v2.3.6 | Instructions-first setup | Windows / AutoHotkey v1.1.37.02

Start with the script's Instructions. They explain the required setup for the exact script variant you selected. Use the LLARS GUI to configure settings; you normally do not need to read or edit a **Config.ini** file.

Contents

1. Before You Start
2. Choosing a Script
3. Using Script Instructions
4. How Settings Are Stored
5. Information and Setup
6. Check Setup
7. Coordinates
8. Hotkeys
9. Colors
10. Timer Settings
11. Optional Settings
12. Run Modes
13. Starting a Run
14. RuneScape Focus and Input Safety
15. Pause, Resume, and Exit
16. Random Sleep
17. Developer Mode and Support
18. Input Settings and AHI
19. Backup, Restore, and Updates
20. When the Game Layout Changes
21. Troubleshooting and Quick Checklist

1. Before You Start

- Keep the complete LLARS folder extracted. Do not run scripts directly from an archive.
- Install **AutoHotkey v1.1.37.02**; AutoHotkey v2 is not compatible.
- Open RuneScape 3 and arrange the interface as you plan to use it.
- Select a bundled script, open **Instructions**, and read its **Before You Start** section.
- Keep the supplied config files with the installation. Do not rename or delete them even when you do not edit them.

Input: LLARS recommends AutoHotInterception (AHI). Standard AutoHotkey is available as a fallback. **Information > Input Settings** shows the active route.

2. Choosing a Script

Open **Script Selector.ahk**, search or filter the list, and choose your script. Favorites and Recent can help you find scripts you have used before. **Normal** and **Menu Entry Swapper (MES)** variants may have different setup requirements.

- Search filters the list while you type; **Ctrl+F** focuses Search.
- Use the view/type filters to narrow the list. **Clear Filters** resets the search and filters.
- Select the exact variant you intend to run. Its Instructions guide applies to that variant.

3. Using Script Instructions

1. In the script's idle LLARS window, click **Instructions** (below **Setup**).
2. Read **Before You Start** for required items, interface settings, camera/standing positions and warnings.
3. Follow the numbered **Steps to Run** in order. Each **[field name]** corresponds to a setting you can select in its Setup editor.
4. Open **Setup > Colors / Coordinates / Hotkeys / Timer** as directed. The Instructions window has the same four shortcuts; unused categories appear disabled.

5. Review **Optional Settings** and **Additional Script Notes** if present, then use **Setup > Check Setup** before pressing **Start**.

> **Important:** Coordinate captures are based on the position specified in the guide. For example, some Agility coordinates must be captured from the tile where you stand *after finishing the previous obstacle*. Follow the script's exact Prime/Main or starting-position instructions.

4. How Settings Are Stored

The shared **LLARS Config.ini** stores project-wide preferences and hotkeys; a script-local **Config.ini** can store that activity's coordinates, hotkeys, colors, timers and options. Some scripts need no local file. You normally access these values through Setup rather than opening the files.

The root configuration uses **config_schema=2**. Current coordinate labels include **[Bank]**, **[Furnace]**, **[Anvil]**, **[Smelter]**, **[Range]**, **[Jewellery]** and **[Bonfire]**. **[Bank Prime]** and **[Bank Main]** remain separate capture positions. Typed hotkeys use short names such as **[Skillbar]** and **[Cape]**.

Older saved field names - for example **[Bank Coords]**, **[Bank Chest]**, **[Furnace Coords]** or **[Skillbar Hotkey]** - remain supported without rewriting the saved file. The **[Pixel Coordinate]**, **[Pixel Coordinate One]** and **[Pixel Coordinate Two]** labels are intentional exceptions and remain unchanged. If both old and new sections exist, the current name takes priority. Select the name shown in Instructions and Setup.

Open **Setup > Script Config** or **Config Settings** only if an instruction explicitly requires manual access, a setting lacks a dedicated editor, or troubleshooting calls for it. Back up first and do not change unknown fields.

5. Information and Setup

Information provides project details and tools, including Input Settings. **Setup** has category editors for Colors, Coordinates, Hotkeys and Timer, plus Script Config, Input Settings and Check Setup. Disabled categories have no applicable settings for the selected script.

6. Check Setup

Use **Setup > Check Setup** to check required settings before running. Missing or invalid entries should be corrected in the named editor. Optional features that are disabled should not be treated as mandatory. Some scripts with no local configuration can show Not Required.

7. Coordinates

1. Open **Setup > Coordinates** and choose the **[field name]** named in Instructions.
2. Stand at the position specified in the guide, move the pointer to the requested RuneScape object, tile or inventory item, and **right-click to capture** it.
3. Repeat for each needed field, keeping separate Prime/Main positions when the guide calls for them.
4. Re-capture positions after moving or resizing RuneScape or changing the relevant UI layout.

8. Hotkeys

Open **Setup > Hotkeys** and assign the game action-bar or bank-preset binding named in the script's Instructions. A label such as **[Skillbar]** is a hotkey field even though it no longer contains the word "Hotkey." Defaults for LLARS-wide actions: **F9 Start**, **F10 Information**, **F11 Setup / Pause / Resume**, and **F12 Exit**. **Ctrl+Shift+D** opens Developer Mode by default.

9. Colors

For color-based scripts, open **Setup > Colors**, choose the named field and capture the pixel/state specified by the guide. Some activities require a particular display setting, such as High Contrast Mode. Re-capture after visual changes; Developer Mode can assist with pixel checks.

10. Timer Settings

Setup > Timer lists the editable timer sections that apply to the selected script. Choose a named timer, enter the minimum and maximum values in **milliseconds**, and save. The minimum must not exceed the maximum. Normal setup should retain default sleep values unless the guide or observed behavior calls for adjustment.

Timer controls are part of the Setup workflow even when the Script Selector summary mentions only Hotkeys, Coordinates and Colors. **1,000 ms = 1 second**. A timer field does not necessarily change how the Start dialog chooses run count versus duration.

11. Optional Settings and Dependencies

Optional features may have their own dependent coordinates, hotkeys, colors or timers. They are only required when the associated feature is enabled. Instructions group optional features separately so the numbered walkthrough focuses on getting the script running.

12. Run Modes

Mode	What you choose
RunCount	A number of repetitions; LLARS estimates duration.
Timer	A run duration.
MultiTimer	A duration for scripts with multiple timed callbacks.
UntilDone / specialized	The script-defined completion behavior.

13. Starting a Run

1. Complete the required **Instructions** and confirm **Check Setup** is ready.
2. Bring RuneScape into the expected starting view, including inventory, camera and tile position.
3. Press **Start** or use the configured Start hotkey; enter the desired count or duration when prompted.
4. Watch the first complete cycle. If a click, menu or movement is wrong, stop and correct the affected setup entry before retrying.

14. RuneScape Focus and Input Safety

LLARS binds framework-managed input to the selected RuneScape window and checks focus/client validity. If the expected window cannot be validated, game-facing input is blocked rather than sent to an arbitrary program. Avoid changing window or interface layouts during a run.

15. Pause, Resume, and Exit

Use the script's supported Pause/Resume control or hotkey to pause and resume. **Exit** stops the script and framework-managed timers. Know the Exit hotkey before beginning a long run.

16. Random Sleep

Random Sleep is an optional shared long-break setting in the root configuration. It can be managed through the supported LLARS configuration controls when needed. Chance determines how often a break may occur; min/max are milliseconds. It is distinct from the script-local timers shown in **Setup > Timer**.

17. Developer Mode and Support

Developer Mode displays diagnostics including active hotkeys, run state, pixel targets, configuration status and recent actions. Use **Copy Support** to generate a support report when troubleshooting. It can be stored under **Logs\LLARS-Support.txt**. Review a report before sharing it.

18. Input Settings and AHI

Information > Input Settings shows the configured and active input backend. **Test AHI** performs a non-invasive readiness check. **Enable / Repair AHI** may need Administrator approval and a restart. **Use Standard AutoHotkey** selects a supported fallback.

19. Backup, Restore, and Updates

Use the tools under **Config Settings** or the **Backup** folder to back up and restore configuration files. An update download also invokes the project backup mechanism. Keep the current installation until a replacement has been saved and validated; do not discard your configuration backup.

20. When the Game Layout Changes

If you move RuneScape, change scaling, alter inventory/action-bar positions or adjust visual settings, coordinates and pixel colors may become stale. Reopen **Instructions**, correct only the affected entries in Setup, and run **Check Setup** again.

21. Troubleshooting and Quick Checklist

Symptom	Check first
Config Error / missing field	Open the named Setup editor; for unsupported advanced fields, use Script Config only if necessary.
Missed click or wrong tile	Revisit the guide's standing-position and coordinate instructions.
Color-based script not responding	Confirm required display mode and recapture the specified pixel.
RuneScape not found / input problem	Verify the selected RuneScape client; open Input Settings and Test AHI.
Need support	Use Developer Mode > Copy Support and include script name/variant.

Quick start: Extract LLARS → install AutoHotkey v1 → choose script → open **Instructions** → complete Setup fields → **Check Setup** → **Start** and observe the first cycle.