
Revision history

| 2017-04-17 | Robin Lamacraft | Original draft | |
|---|-----------------|---|--|
| 2018-05-26 | Rod Thompson | Add diagram, actions | |
| 2018-06-12 | Rod Thompson | Replace GUI_PanelConfigEdit with GUI_Select Configuration | |
| | | Replace BR_PanelConfig with BR_WindowConfig | |
| 2018-06-21 Rod Thompson Replace Graphic | | Replace Graphic | |
| | | Revise REQUIRED SERVICES – Dependencies | |
| | | Add PROCESS FLOW CHART | |
| 2018-10-12 | Rod Thompson | Revise REQUIRED SERVICES – Remove 03.68 | |
| | | Replace WINDOWS INTERACTION MAP | |
| | | Replace Graphic | |
| | | Add Location/Size information | |
| | | Add Window adjustment to EVENT ACTIONS | |
| | | Add LOGGING section | |
| 2019-04-05 | Don Ferguson | Replace mockup with real screen | |

SCOPE

This GUI module displays the text of Help for the window calling the 'Help'. It also will provide web links to expanded content that can be displayed in a web browser.

LOOK AND FEEL



GUI Help Window

The Help window has 4 sections:

- Heading section with:
 - o The text field that shows the name of the window from which it was called

Topic Description area to be populated with the relevant content. Also the On-line Help URL field is populated with the URL for that topic within the HRE On-line Help Wiki

- <u>Topic Description</u> section on the right is scrollable. In this Topic Description space the description of the currently selected topic is displayed
- On-Line Help section below has a field that is populated with the current topic's URL on the HRE Wiki website. Clicking on that field will open a browser and view that topic on-line.

Shape, Size, Color, Layout etc. determined in design.

On screen location
Inherited from the calling window's Help icon
On screen location and scale are the only User changeable settings.

USED BY: Almost any GUI module.

ACTIONS

The fundamental operations are:

- 1. Open the Help window according to its saved Panel Layout (BR_WindowConfig)
- 2. Populate the display with list of topics for that window
- 3. Perform content updates according to topic selection.

DATA CONTROLLED BY THIS MODULE

None.

REQUIRED DATA CONTROLLED BY OTHER MODULES

Parameters passed to this module are:

- 1. Title of calling Window
- 2. Help topic to be looked up and description displayed.

REQUIRED SERVICES – Dependencies

| First-Order Dependencies | Second-Order Dependencies | Higher-Order Dependencies |
|--------------------------|---------------------------|---------------------------|
| | | |
| 07.24 BR_Setting | BR_AppData | |
| | BR_UserData | |
| | 07.02 BR_EntityLink | NIL |
| 07.17 BR_WindowConfig | 07.06 BR_GuiElement | 07.01 BR_EncodedString |
| | | 07.02 BR_EntityLink |
| | | BR_FieldTranslation |
| | | 07.16 BR_MessagePatterns |
| | 07.02 BR_EntityLink | NIL |
| | 07.29 BR_Translation | 07.02 BR_EntityLink |
| | | BR_Field |
| | | 07.06 BR_GuiElement |
| | | 07.16 BR_MessagePatterns |
| | BR_FieldTranslation | |
| | 07.16 BR_MessagePatterns | 07.02 BR_EntityLink |
| | | 07.01 BR_EncodedString |

| | | 07.24 BR_Setting |
|---------------------|--------------------------|--------------------------|
| | | GUI_Translation |
| 07.07 BR_Help | 07.29 BR_Translation | 07.02 BR_EntityLink |
| | | BR_Field |
| | | 07.06 BR_GuiElement |
| | | 07.16 BR_MessagePatterns |
| | 07.21 BR_Project | 07.06 BR_GuiElement |
| | | 07.02 BR_EntityLink |
| | | 07.29 BR_Translation |
| | | BR_FieldDefinition |
| | 07.01 BR_EncodedString | NIL |
| | 07.24 BR_Setting | BR_AppData |
| | | BR_UserData |
| | | 07.02 BR_EntityLink |
| | BR_FieldTranslation | |
| | 07.26 BR_Substitution | 07.02 BR_EntityLink |
| | | 07.29 BR_Translation |
| | 07.12 BR_Menu | NIL |
| | 07.25 BR_Schema | 07.02 BR_EntityLink |
| | | BR_UserTranslation |
| | | BR_FieldTranslation |
| | 07.28 BR_User | |
| | 07.16 BR_MessagePatterns | 07.02 BR_EntityLink |
| | | 07.01 BR_EncodedString |
| _ | | Call Stack |
| | | 07.24 BR_Setting |
| | | GUI_Translation |
| 07.02 BR_EntityLink | Needed | |

APPLICATION PROGRAMMING INTERFACE (API)

Parameters passed to this module are:

- 1. Title of calling Window
- 2. Help topic to be looked up and description displayed.

LOGGING

General use of this module will not create log entries.

Setting changes to this Window (location and size) will create log entries.

EVENT ACTIONS

- Keyboard actions
 Not applicable
- 2) Mouse actions

Drag and drop mouse actions to move and resize the window Setting changes saved to database for User>Project>Window Left key

- a. Mouse hover over the slider bar, hold key down and drag slider bar up or down
- b. Mouse key tap in slider bar box causes up and down movement
- c. Click on an item in the Topic Selection panel selects that item
- d. Click on the On-line field URL opens a web browser to the HRE Wiki website, viewing the selected topic
- e. Click on the 'Close' button closes the window

To be determined

- 3) Icon actions
 - a. left mouse key click on icons in the Window Control group:
 - a. 'X' icon (closes the window)
 - b. 'Box' icon

Toggles the window size between full screen, and the preset window size

- c. 'Dash' icon
 - Minimizes the window, to an icon on the screen toolbar.

A click on the toolbar icon restores the display to its previous setting

4) Keyboard shortcuts

To be determined

WARNING CONDITIONS

1. Need Details.

ERROR CONDITIONS

1. Need Details.

WINDOW INTERACTION MAP

