





*Steps to download and Install
Jupyter Notebook and Pytorch*





Python Environment



System Properties



Python Environment



Python Environment

Ensure you have a working pip

```
PS C:\Users\User> python --version
Python 3.11.5
PS C:\Users\User> pip --version
pip 23.3 from C:\Python311\Lib\site-packages\pip (python 3.11)
PS C:\Users\User>
```



Python Environment

Not working!!

<https://pip.pypa.io/en/stable/installation/>

Steps to download and install Jupyter Notebook

Jupyter Notebook

Install the classic Jupyter Notebook with:

```
pip install notebook
```

To run the notebook:

```
jupyter notebook
```

Steps to download and install Pytorch



PyTorch

<https://pytorch.org>

PyTorch

PyTorch Geometric is a library for deep learning on irregular input data such as graphs, point clouds, and manifolds. skorch. skorch is a high-level library for ...

Previous versions

ROCM 5.6 (Linux only) pip install torch==2.1.1 torchvision==0.16 ...

PyTorch 2.0

What is PT 2.0? 2.0 is the latest PyTorch version. PyTorch 2.0 ...

Get Started

PyTorch 2.0 - Previous versions - Tensors - Via Cloud Partners

Installation

... download.pytorch.org/whl/nightly/cpu. Running pip install ...

Steps to download and install Pytorch

PyTorch Build	Stable (2.1.2)		Preview (Nightly)	
Your OS	Linux	Mac	Windows	
Package	Conda	Pip	LibTorch	Source
Language	Python		C++ / Java	
Compute Platform	CUDA 11.8	CUDA 12.1	ROCm 5.6	CPU
Run this Command:	<code>pip3 install torch torchvision torchaudio</code>			

To download, go to the directory and use:

`pip3 download torch torchvision torchaudio`

Steps to download and install Pytorch

PyTorch Build	Stable (2.1.2)		Preview (Nightly)	
Your OS	Linux	Mac	Windows	
Package	Conda	Pip	LibTorch	Source
Language	Python		C++ / Java	
Compute Platform	CUDA 11.8	CUDA 12.1	ROCm 5.6	CPU
Run this Command:	<pre>pip3 install torch torchvision torchaudio --index-url https://download.pytorch.org/whl/cu118</pre>			

Steps to download and install Pytorch

PyTorch Build	Stable (2.1.2)		Preview (Nightly)	
Your OS	Linux	Mac	Windows	
Package	Conda	Pip	LibTorch	Source
Language	Python		C++ / Java	
Compute Platform	CUDA 11.8	CUDA 12.1	ROCm 5.6	CPU
Run this Command:	<pre>pip3 install torch torchvision torchaudio --index-url https://download.pytorch.org/whl/cu118</pre>			