


01). Karachi (Router): se 0/1/0, IP: 192.168.1.1

02). Lahore(Router): se 0/1/0, IP: 192.168.1.2



The screenshot shows the Karachi router's CLI interface. The window title is "Karachi". The tabs are "Physical", "Config", and "CLI". The title bar of the terminal window is "IOS Command Line Interface". The terminal output shows the following commands and responses:

```
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1,
RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---


Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Hammadullah
Hammadullah(config)#int se 0/1/0
Hammadullah(config-if)#ip address 192.168.1.1 255.255.255.0
Hammadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

At the bottom of the window, there are "Copy" and "Paste" buttons.



The screenshot shows the Lahore router's CLI interface. The window title is "Lahore". The tabs are "Physical", "Config", and "CLI". The title bar of the terminal window is "IOS Command Line Interface". The terminal output shows the following commands and responses:

```
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Hammadullah
Hammadullah(config)#int se 0/1/0
Hammadullah(config-if)#ip address 192.168.1.2 255.255.255.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up
```

At the bottom of the window, there are "Copy" and "Paste" buttons.

03). Karachi (Fa Connection): Fa 0/0, IP: 11.11.1.1

Karachi

Physical Config CLI

IOS Command Line Interface

```
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Hammadullah
Hammadullah(config)#int se 0/1/0
Hammadullah(config-if)#ip address 192.168.1.1 255.255.255.0
Hammadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up

Hammadullah#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#interface FastEthernet0/0
Hammadullah(config-if)#int Fa 0/0
Hammadullah(config-if)#ip address 11.11.1.1 255.0.0.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
|
```

Copy Paste

04). PC0: 11.11.1.2

PC0

Physical Config Desktop Custom Interface

FastEthernet0

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 000C.CF50.1C54

IP Configuration

☐ DHCP

☒ Static

IP Address 11.11.1.2

Subnet Mask 255.0.0.0

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

Link Local Address: FE80::20C:CFFF:FE50:1C54

05).PC1: IP: 11.11.1.2

06). Lahore (Fast Ethernet Connection): Fa 0/0, IP: 12.12.1.1

PC1

PhysicalConfigDesktopCustom Interface

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

FastEthernet0

Port Status

☒ On

Bandwidth

☐ 100 Mbps☐ 10 Mbps☒ Auto

Duplex

☐ Half Duplex☒ Full Duplex☒ Auto

MAC Address

0060.3E4A.4C00

IP Configuration

☐ DHCP

☒ Static

IP Address

11.11.1.3

Subnet Mask

255.0.0.0

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

Link Local Address: FE80::260:3EFF:FE4A:4C00

Lahore

PhysicalConfigCLI

IOS Command Line Interface

```
Hammadullah>en
Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int Fa 0/0
Hammadullah(config-if)#ip address 12.12.1.1 255.0.0.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy

Paste

07). PC2: 12.12.1.2

08). PC3: IP: 12.12.1.3

PC2

Physical Config Desktop Custom Interface

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

FastEthernet0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 000C.CF2C.053E

IP Configuration

☐ DHCP

☒ Static

IP Address 12.12.1.2

Subnet Mask 255.0.0.0

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

Link Local Address: FE80::20C:CFFF:FE2C:53E

PC3

Physical Config Desktop Custom Interface

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

FastEthernet0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 0003.E49C.D203

IP Configuration

☐ DHCP

☒ Static

IP Address 12.12.1.3

Subnet Mask 255.0.0.0

IPv6 Configuration

☐ DHCP


☐ Auto Config

☒ Static

IPv6 Address

Link Local Address: FE80::203:E4FF:FE9C:D203

09). Islamabad (Router): se 0/1/0, IP: 194.10.10.1



The screenshot shows the Islamabad router's CLI interface. The window title is 'Islamabad'. The tabs are 'Physical', 'Config', and 'CLI'. The main text area displays the following commands and output:

```
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1,
RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n


Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Hammadullah
Hammadullah(config)#int se 0/1/0
Hammadullah(config-if)#ip address 194.10.10.1 255.255.255.0
Hammadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

At the bottom of the window, there are 'Copy' and 'Paste' buttons.

10). Peshawer (Router): se 0/1/0, IP: 194.10.10.2



The screenshot shows the Peshawer router's CLI interface. The window title is 'Peshawer'. The tabs are 'Physical', 'Config', and 'CLI'. The main text area displays the following commands and output:

```
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Hammadullah
Hammadullah(config)#int se 0/1/0
Hammadullah(config-if)#ip address 194.10.10.2 255.255.255.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up
```

At the bottom of the window, there are 'Copy' and 'Paste' buttons.

11). Islamabad (Fa Connection): Fa 0/0, IP: 13.13.1.1

12). PC4: IP: 13.13.1.2

Islamabad

PhysicalConfigCLI

IOS Command Line Interface

```
Hammadullah(config-if)#ip address 194.10.10.1 255.255.255.0
Hammadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up

Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int Fa 0/0
Hammadullah(config-if)#ip address 13.13.1.1 255.0.0.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

CopyPaste

PC4

PhysicalConfigDesktopCustom Interface

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

FastEthernet0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 0060.47DB.6DAE

IP Configuration

☐ DHCP

☒ Static

IP Address 13.13.1.2

Subnet Mask 255.0.0.0

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

Link Local Address: FE80::260:47FF:FEDB:6DAE

13). PC5: IP: 13.13.1.4

PC5

Physical Config Desktop Custom Interface

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

FastEthernet0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 0001.9637.4967

IP Configuration

☐ DHCP

☒ Static

IP Address 13.13.1.4

Subnet Mask 255.0.0.0

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

Link Local Address: FE80::201:96FF:FE37:4967

14). Peshawer (Fa Connection): Fa 0/0, IP: 14.14.1.1

Peshawer

Physical Config CLI

IOS Command Line Interface

```
Hammadullah(config-if)#ip address 194.10.10.2 255.255.255.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up

Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int Fa 0/0
Hammadullah(config-if)#ip address 14.14.1.1 255.0.0.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste

15). PC6: IP: 14.14.1.2

PC6

Physical Config Desktop Custom Interface

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

FastEthernet0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 0060.3E34.EC85

IP Configuration

☐ DHCP

☒ Static

IP Address 14.14.1.2

Subnet Mask 255.0.0.0

IPv6 Configuration

☐ DHCP

☐ Auto Config

☒ Static

IPv6 Address

Link Local Address: FE80::260:3EFF:FE34:EC85

16). PC7: IP: 14.14.1.3

PC7

Physical Config Desktop Custom Interface

GLOBAL

Settings

Algorithm Settings

INTERFACE

FastEthernet0

FastEthernet0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 00D0.BA34.0271

IP Configuration

☐ DHCP

☒ Static

IP Address 14.14.1.3

Subnet Mask 255.0.0.0

IPv6 Configuration

☐ DHCP


☐ Auto Config

☒ Static

IPv6 Address

Link Local Address: FE80::2D0:BAFF:FE34:271

17). Karachi (Router): se 0/1/1, IP: 192.20.20.1



```
Karachi
Physical Config CLI
IOS Command Line Interface


Press RETURN to get started.

Hammadullah>en
Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/1/1
Hammadullah(config-if)#ip address 192.20.20.1 255.255.255.0
Hammadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/1, changed state to down
Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste

18). Islamabad (Router): se 0/1/1, IP: 192.20.20.2



```
Islamabad
Physical Config CLI
IOS Command Line Interface

Hammadullah>en
Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/1/1
Hammadullah(config-if)#ip address 192.20.20.2 255.255.255.0
Hammadullah(config-if)#no shutdown


Hammadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state to up
```

Copy Paste

19). Lahore (Router): se 0/1/1, IP: 193.20.20.1



```
Lahore
Physical Config CLI
IOS Command Line Interface


Hammadullah>en
Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/1/1
Hammadullah(config-if)#ip address 193.20.20.1
^
% Invalid input detected at '^' marker.

Hammadullah(config-if)#ip address 193.20.20.1 255.255.255.0
Hammadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/1, changed state to down
Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste

20). Peshawer (Router): se 0/1/1, IP: 193.20.20.2



```
Peshawer
Physical Config CLI
IOS Command Line Interface

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console

Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/1/1
Hammadullah(config-if)#exit
Hammadullah(config)#end
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console


Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/1/1
Hammadullah(config-if)#ip address 193.20.20.2 255.255.255.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste

21). Karachi (Router): se 0/0/0, IP: 192.10.10.1



```
Karachi
Physical Config CLI
IOS Command Line Interface
Hammadullah>en
Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/0/0
Hammadullah(config-if)#ip address 192.10.10.1 255.255.255.0
Hammadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console


%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/0/0
Hammadullah(config-if)#ip address 192.10.10.1 255.255.255.0
Hammadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste

22). Peshawer (Router): se 0/0/0, IP: 192.10.10.2



```
Peshawer
Physical Config CLI
IOS Command Line Interface
Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/1/1
Hammadullah(config-if)#ip address 193.20.20.2 255.255.255.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state to up


Hammadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah(config)#int se 0/0/0
Hammadullah(config-if)#ip address 192.10.10.2 255.255.255.0
Hammadullah(config-if)#no shutdown

Hammadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

Hammadullah(config-if)#ex
Hammadullah(config)#ex
Hammadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste

23). Islamabad (Router): se 0/0/0, IP: 193.10.10.1



Islamabad

Physical Config CLI

IOS Command Line Interface

```
Hamadullah>en
Hamadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hamadullah(config)#int se 0/1/1
Hamadullah(config-if)#ip address 192.20.20.2 255.255.255.0
Hamadullah(config-if)#no shutdown

Hamadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up

Hamadullah(config-if)#ex
Hamadullah(config)#ex
Hamadullah#
%SYS-5-CONFIG_I: Configured from console by console


%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state to up

Hamadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hamadullah(config)#int se 0/0/0
Hamadullah(config-if)#ip address 193.10.10.1 255.255.255.0
Hamadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Hamadullah(config-if)#ex
Hamadullah(config)#ex
Hamadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste

24). Lahore (Router): se 0/0/0, IP: 193.10.10.2



Lahore

Physical Config CLI

IOS Command Line Interface

```
% Invalid input detected at '^' marker.

Hamadullah(config-if)#ip address 193.20.20.1 255.255.255.0
Hamadullah(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/1, changed state to down
Hamadullah(config-if)#ex
Hamadullah(config)#ex
Hamadullah#
%SYS-5-CONFIG_I: Configured from console by console

%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state to up


Hamadullah#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hamadullah(config)#int se 0/0/0
Hamadullah(config-if)#ip address 193.10.10.2 255.255.255.0
Hamadullah(config-if)#no shutdown

Hamadullah(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

Hamadullah(config-if)#ex
Hamadullah(config)#ex
Hamadullah#
%SYS-5-CONFIG_I: Configured from console by console
```

Copy Paste


Whole Diagram:



PDU ListWindow

PDU List Window										
Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	Karachi	Lahore	ICMP		0.000	N	0	(edit)	
	Successful	Karachi	Lahore	ICMP		0.000	N	1	(edit)	
	Successful	Lahore	Karachi	ICMP		0.000	N	2	(edit)	
	Successful	Karachi	PC0	ICMP		0.000	N	3	(edit)	
	Successful	PC0	Karachi	ICMP		0.000	N	4	(edit)	
	Successful	Karachi	PC1	ICMP		0.000	N	5	(edit)	
	Successful	PC1	Karachi	ICMP		0.000	N	6	(edit)	
	Successful	PC0	Karachi	ICMP		0.000	N	7	(edit)	
	Successful	PC1	Karachi	ICMP		0.000	N	8	(edit)	
	Successful	PC2	Lahore	ICMP		0.000	N	9	(edit)	
	Successful	PC3	Lahore	ICMP		0.000	N	10	(edit)	
	Successful	PC4	Islamabad	ICMP		0.000	N	11	(edit)	
	Successful	PC5	Islamabad	ICMP		0.000	N	12	(edit)	
	Successful	PC6	Peshawer	ICMP		0.000	N	13	(edit)	
	Successful	PC7	Peshawer	ICMP		0.000	N	14	(edit)	
	Successful	Karachi	Lahore	ICMP		0.000	N	15	(edit)	
	Successful	Karachi	Islamabad	ICMP		0.000	N	16	(edit)	
	Successful	Karachi	Peshawer	ICMP		0.000	N	17	(edit)	
	Successful	Islama...	Lahore	ICMP		0.000	N	18	(edit)	
	Successful	Islama...	Peshawer	ICMP		0.000	N	19	(edit)	
	Successful	Pesha...	Lahore	ICMP		0.000	N	20	(edit)	

Ping PC0:



The screenshot shows the 'PC0' window in Packet Tracer. The 'Desktop' tab is selected, and a 'Command Prompt' window is open. The command 'ping 11.11.1.1' has been executed, resulting in four successful replies with 0ms round trip times. The ping statistics show 4 packets sent, 4 received, and 0% loss.

```
Packet Tracer PC Command Line 1.0
PC>ping 11.11.1.1


Pinging 11.11.1.1 with 32 bytes of data:

Reply from 11.11.1.1: bytes=32 time=0ms TTL=255
Reply from 11.11.1.1: bytes=32 time=0ms TTL=255
Reply from 11.11.1.1: bytes=32 time=0ms TTL=255
Reply from 11.11.1.1: bytes=32 time=0ms TTL=255

Ping statistics for 11.11.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

PC>
```

Ping PC1:



The screenshot shows the 'PC1' window in Packet Tracer. The 'Desktop' tab is selected, and a 'Command Prompt' window is open. The command 'ping 11.11.1.1' has been executed, resulting in four successful replies with 1ms round trip times. The ping statistics show 4 packets sent, 4 received, and 0% loss.

```
Packet Tracer PC Command Line 1.0
PC>ping 11.11.1.1


Pinging 11.11.1.1 with 32 bytes of data:

Reply from 11.11.1.1: bytes=32 time=1ms TTL=255
Reply from 11.11.1.1: bytes=32 time=0ms TTL=255
Reply from 11.11.1.1: bytes=32 time=1ms TTL=255
Reply from 11.11.1.1: bytes=32 time=0ms TTL=255

Ping statistics for 11.11.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms

PC>
```

Ping PC2:



The screenshot shows the PC2 desktop environment with a 'Command Prompt' window open. The window title is 'PC2'. The command prompt displays the output of the command 'ping 12.12.1.1'. The output shows four successful replies from 12.12.1.1 with 32 bytes of data. The ping statistics for 12.12.1.1 are: Packets: Sent = 4, Received = 4, Lost = 0 (0% loss), and Approximate round trip times in milli-seconds: Minimum = 0ms, Maximum = 16ms, Average = 4ms.

```
Packet Tracer PC Command Line 1.0
PC>ping 12.12.1.1


Pinging 12.12.1.1 with 32 bytes of data:

Reply from 12.12.1.1: bytes=32 time=0ms TTL=255
Reply from 12.12.1.1: bytes=32 time=16ms TTL=255
Reply from 12.12.1.1: bytes=32 time=0ms TTL=255
Reply from 12.12.1.1: bytes=32 time=0ms TTL=255

Ping statistics for 12.12.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 16ms, Average = 4ms

PC>
```

Ping PC3:



The screenshot shows the PC3 desktop environment with a 'Command Prompt' window open. The window title is 'PC3'. The command prompt displays the output of the command 'ping 12.12.1.1'. The output shows four successful replies from 12.12.1.1 with 32 bytes of data. The ping statistics for 12.12.1.1 are: Packets: Sent = 4, Received = 4, Lost = 0 (0% loss), and Approximate round trip times in milli-seconds: Minimum = 0ms, Maximum = 0ms, Average = 0ms.

```
Packet Tracer PC Command Line 1.0
PC>ping 12.12.1.1


Pinging 12.12.1.1 with 32 bytes of data:

Reply from 12.12.1.1: bytes=32 time=0ms TTL=255
Reply from 12.12.1.1: bytes=32 time=0ms TTL=255
Reply from 12.12.1.1: bytes=32 time=0ms TTL=255
Reply from 12.12.1.1: bytes=32 time=0ms TTL=255

Ping statistics for 12.12.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

PC>
```

Ping PC4:



The screenshot shows the Packet Tracer PC Command Line interface for PC4. The 'Desktop' tab is selected. The command prompt displays the output of the command 'ping 13.13.1.1'. The output shows four successful replies from 13.13.1.1 with 32 bytes of data, each with a time of 0ms and TTL of 255. The ping statistics for 13.13.1.1 show 4 packets sent, 4 received, 0 lost (0% loss), and approximate round trip times of 0ms minimum, 1ms maximum, and 0ms average.

```
Packet Tracer PC Command Line 1.0
PC>ping 13.13.1.1


Pinging 13.13.1.1 with 32 bytes of data:

Reply from 13.13.1.1: bytes=32 time=0ms TTL=255
Reply from 13.13.1.1: bytes=32 time=0ms TTL=255
Reply from 13.13.1.1: bytes=32 time=0ms TTL=255
Reply from 13.13.1.1: bytes=32 time=1ms TTL=255

Ping statistics for 13.13.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms

PC>
```

ping PC5:



The screenshot shows the Packet Tracer PC Command Line interface for PC5. The 'Desktop' tab is selected. The command prompt displays the output of the command 'ping 13.13.1.3'. The output shows four 'Request timed out.' messages. The ping statistics for 13.13.1.3 show 4 packets sent, 0 received, 4 lost (100% loss). The command prompt then displays the output of the command 'ping 13.13.1.1'. The output shows four successful replies from 13.13.1.1 with 32 bytes of data, each with a time of 0ms and TTL of 255. The ping statistics for 13.13.1.1 show 4 packets sent, 4 received, 0 lost (0% loss), and approximate round trip times of 0ms minimum, 1ms maximum, and 0ms average.

```
Packet Tracer PC Command Line 1.0
PC>ping 13.13.1.3

Pinging 13.13.1.3 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 13.13.1.3:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

PC>ping 13.13.1.1


Pinging 13.13.1.1 with 32 bytes of data:

Reply from 13.13.1.1: bytes=32 time=0ms TTL=255
Reply from 13.13.1.1: bytes=32 time=0ms TTL=255
Reply from 13.13.1.1: bytes=32 time=1ms TTL=255
Reply from 13.13.1.1: bytes=32 time=0ms TTL=255

Ping statistics for 13.13.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms

PC>
```

Ping PC6:



The screenshot shows the Packet Tracer PC Command Line interface for PC6. The window has tabs for Physical, Config, Desktop, and Custom Interface. The Desktop tab is active, displaying a Command Prompt window. The Command Prompt shows the command 'ping 14.14.1.1' being executed. The output indicates that the ping was successful, with 4 packets sent, 4 received, and 0% loss. The approximate round trip times are: Minimum = 0ms, Maximum = 1ms, Average = 0ms.

```
Packet Tracer PC Command Line 1.0
PC>ping 14.14.1.1


Pinging 14.14.1.1 with 32 bytes of data:

Reply from 14.14.1.1: bytes=32 time=0ms TTL=255
Reply from 14.14.1.1: bytes=32 time=0ms TTL=255
Reply from 14.14.1.1: bytes=32 time=1ms TTL=255
Reply from 14.14.1.1: bytes=32 time=0ms TTL=255

Ping statistics for 14.14.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms

PC>
```

Ping PC7:



The screenshot shows the Packet Tracer PC Command Line interface for PC7. The window has tabs for Physical, Config, Desktop, and Custom Interface. The Desktop tab is active, displaying a Command Prompt window. The Command Prompt shows the command 'ping 14.14.1.1' being executed. The output indicates that the ping was successful, with 4 packets sent, 4 received, and 0% loss. The approximate round trip times are: Minimum = 0ms, Maximum = 2ms, Average = 0ms.

```
Packet Tracer PC Command Line 1.0
PC>ping 14.14.1.1

Pinging 14.14.1.1 with 32 bytes of data:

Reply from 14.14.1.1: bytes=32 time=0ms TTL=255
Reply from 14.14.1.1: bytes=32 time=1ms TTL=255
Reply from 14.14.1.1: bytes=32 time=2ms TTL=255
Reply from 14.14.1.1: bytes=32 time=0ms TTL=255

Ping statistics for 14.14.1.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 2ms, Average = 0ms

PC>
```