




For Checking Connectivity:

```

PC2
Physical Config Desktop Programming Attributes
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 192.168.3.3

Pinging 192.168.3.3 with 32 bytes of data:

Request timed out.
Reply from 192.168.3.3: bytes=32 time=3ms TTL=125
Reply from 192.168.3.3: bytes=32 time=2ms TTL=125
Reply from 192.168.3.3: bytes=32 time=11ms TTL=125

Ping statistics for 192.168.3.3:
    Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 2ms, Maximum = 11ms, Average = 5ms


C:\>ping 192.168.3.3

Pinging 192.168.3.3 with 32 bytes of data:


Reply from 192.168.3.3: bytes=32 time=3ms TTL=125
Reply from 192.168.3.3: bytes=32 time=20ms TTL=125
Reply from 192.168.3.3: bytes=32 time=10ms TTL=125
Reply from 192.168.3.3: bytes=32 time=2ms TTL=125

Ping statistics for 192.168.3.3:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 2ms, Maximum = 20ms, Average = 8ms

C:\>
    
```



On Router0 we have NAT and ACL



```
Router0
Physical Config CLI Attributes
IOS Command Line Interface
Hammad_15398_R0(config)#router ospf 10
Hammad_15398_R0(config-router)#network 192.168.1.0 0.0.0.255 area 0
Hammad_15398_R0(config-router)#network 10.10.10.0 0.0.0.3 area 0
Hammad_15398_R0(config-router)#
00:16:55: %OSPF-5-ADJCHG: Process 10, Nbr 192.168.2.1 on Serial0/3/0 from LOADING to
FULL, Loading Done

Hammad_15398_R0(config-router)#exit
Hammad_15398_R0(config)#exit
Hammad_15398_R0#
%SYS-5-CONFIG_I: Configured from console by console

Hammad_15398_R0#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammad_15398_R0(config)#ip nat pool Hammad_15398 50.50.50.1 50.50.50.5 netmask
255.255.255.0
Hammad_15398_R0(config)#access-list 1 permit 192.168.1.0 0.0.0.255
Hammad_15398_R0(config)#ip nat inside source list 1 pool Hammad_15398 overload
Hammad_15398_R0(config)#interface fa0/0
Hammad_15398_R0(config-if)#ip nat inside
Hammad_15398_R0(config-if)#exit
Hammad_15398_R0(config)#interface se0/3/0
Hammad_15398_R0(config-if)#ip nat outside
Hammad_15398_R0(config-if)#end
Hammad_15398_R0#
%SYS-5-CONFIG_I: Configured from console by console

Hammad_15398_R0#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammad_15398_R0(config)#router ospf 10
Hammad_15398_R0(config-router)#network 50.50.50.0 0.0.0.255 area 0
Hammad_15398_R0(config-router)#end
Hammad_15398_R0#
%SYS-5-CONFIG_I: Configured from console by console

Hammad_15398_R0#clear ip nat translation
% Incomplete command.
Hammad_15398_R0#clear ip nat translation *
Hammad_15398_R0#
```

Copy Paste

Router1

Physical Config **CLI** Attributes


IOS Command Line Interface

```
Hammad_15398R1>en
Hammad_15398R1#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammad_15398R1(config)#router ospf 10
Hammad_15398R1(config-router)#network 50.50.50.0 0.0.0.255 area 0
Hammad_15398R1(config-router)#end
Hammad_15398R1#
%SYS-5-CONFIG_I: Configured from console by console

Hammad_15398R1#en
Hammad_15398R1#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammad_15398R1(config)#router ospf 10
Hammad_15398R1(config-router)#network 192.168.2.0 0.0.0.255 area 0
Hammad_15398R1(config-router)#network 10.10.10.0 0.0.0.3 area 0
Hammad_15398R1(config-router)#network 10.10.11.0 0.0.0.3 area 0
Hammad_15398R1(config-router)#network 50.50.50.0 0.0.0.255 area 0
Hammad_15398R1(config-router)#end
Hammad_15398R1#
%SYS-5-CONFIG_I: Configured from console by console

Hammad_15398R1#write
Building configuration...
[OK]
Hammad_15398R1#
```

Copy Paste



Router3

Physical Config **CLI** Attributes

IOS Command Line Interface

```
Hammad_15398_R3>en
Hammad_15398_R3#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammad_15398_R3(config)#router ospf 10
Hammad_15398_R3(config-router)#network 50.50.50.0 0.0.0.255 area 0
Hammad_15398_R3(config-router)#end
Hammad_15398_R3#
%SYS-5-CONFIG_I: Configured from console by console

Hammad_15398_R3#en
Hammad_15398_R3#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammad_15398_R3(config)#router ospf 10
Hammad_15398_R3(config-router)#network 192.168.4.0 0.0.0.255 area 0
Hammad_15398_R3(config-router)#network 10.10.12.0 0.0.0.3 area 0
Hammad_15398_R3(config-router)#network 50.50.50.0 0.0.0.255 area 0
Hammad_15398_R3(config-router)#end
Hammad_15398_R3#
%SYS-5-CONFIG_I: Configured from console by console

Hammad_15398_R3#wite
Translating "wite"...domain server (255.255.255.255)
% Unknown command or computer name, or unable to find computer address

Hammad_15398_R3#write
Building configuration...
[OK]
Hammad_15398_R3#
```

Copy Paste