




PDU List Window

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC1	PC5	ICMP		0.000	N	0	(edit)	(delete)
	Successful	PC1	PC14	ICMP		0.000	N	1	(edit)	(delete)
	Successful	PC1	PC18	ICMP		0.000	N	2	(edit)	(delete)
	Successful	PC1	PC10	ICMP		0.000	N	3	(edit)	(delete)
	Successful	PC7	PC3	ICMP		0.000	N	4	(edit)	(delete)
	Successful	PC6	PC13	ICMP		0.000	N	5	(edit)	(delete)
	Successful	PC5	PC9	ICMP		0.000	N	6	(edit)	(delete)
	Successful	PC4	PC19	ICMP		0.000	N	7	(edit)	(delete)
	Successful	PC17	PC3	ICMP		0.000	N	8	(edit)	(delete)
	Successful	PC18	PC10	ICMP		0.000	N	9	(edit)	(delete)
	Successful	PC8	PC2	ICMP		0.000	N	10	(edit)	(delete)
	Successful	PC11	PC18	ICMP		0.000	N	11	(edit)	(delete)
	Successful	PC8	PC13	ICMP		0.000	N	12	(edit)	(delete)
	Successful	PC6	PC17	ICMP		0.000	N	13	(edit)	(delete)

 Hamadullah1
Physical Config CLI
IOS C
Compiled Wed 18-Jul-07 06:21 by pt_rel_team

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#Hostname Hamadullah1
Hamadullah1(config)#int Fa0/0
Hamadullah1(config-if)#ip address 192.168.1.1 255.255.255.248
Hamadullah1(config-if)#no shutdown

Hamadullah1(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hamadullah1(config-if)#int Se0/3/0
Hamadullah1(config-if)#ip address 10.10.10.1 255.255.255.252
Hamadullah1(config-if)#clockrate 64000
^
% Invalid input detected at '^' marker.

Hamadullah1(config-if)#clock rate 64000
Hamadullah1(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/3/0, changed state to down
Hamadullah1(config-if)#exit
Hamadullah1(config)#router eigrp 15398
Hamadullah1(config-router)#network 192.168.1.0 0.0.0.7
Hamadullah1(config-router)#network 10.10.10.0 0.0.0.3
Hamadullah1(config-router)#
%LINK-5-CHANGED: Interface Serial0/3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/3/0, changed state to up

%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.2 (Serial0/3/0) is up: new adjacency

%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.2 (Serial0/3/0) is resync: graceful restart

 Hammadullah5

Physical Config CLI

IO

```
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#Hostname Hammadullah5
Hammadullah5(config)#int Fa0/0
Hammadullah5(config-if)#ip address 192.168.1.9 255.255.255.248
Hammadullah5(config-if)#no shutdown

Hammadullah5(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah5(config-if)#int Se0/3/0
Hammadullah5(config-if)#ip address 10.10.10.2 255.255.255.252
Hammadullah5(config-if)#no shutdown

Hammadullah5(config-if)#
%LINK-5-CHANGED: Interface Serial0/3/0, changed state to up

Hammadullah5(config-if)#int
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/3/0, changed state to up

^
% Invalid input detected at '^' marker.

Hammadullah5(config-if)#int Se0/3/1
Hammadullah5(config-if)#ip address 10.10.10.5 255.255.255.252
Hammadullah5(config-if)#clock rate 64000
Hammadullah5(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/3/1, changed state to down
Hammadullah5(config-if)#exit
Hammadullah5(config)#router eigrp 15398
Hammadullah5(config-router)#network 192.168.1.8 0.0.0.7
Hammadullah5(config-router)#network 10.10.10.0 0.0.0.3
Hammadullah5(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.1 (Serial0/3/0) is up: new adjacency

Hammadullah5(config-router)#network 10.10.10.4 0.0.0.3
Hammadullah5(config-router)#no auto-summary
Hammadullah5(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.1 (Serial0/3/0) resync: summary configured

Hammadullah5(config-router)#
%LINK-5-CHANGED: Interface Serial0/3/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/3/1, changed state to up

%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.6 (Serial0/3/1) is up: new adjacency
```

 Hammadullah3

Physical Config CLI

IOS Co

```
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#Hostname Hammadullah3
Hammadullah3(config)#int Fa0/0
Hammadullah3(config-if)#ip address 192.168.1.17 255.255.255.248
Hammadullah3(config-if)#no shutdown

Hammadullah3(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah3(config-if)#int Se0/3/0
Hammadullah3(config-if)#ip address 10.10.10.6 255.255.255.252
Hammadullah3(config-if)#no shutdown

Hammadullah3(config-if)#
%LINK-5-CHANGED: Interface Serial0/3/0, changed state to up

Hammadullah3(config-if)#int Se0/3/1
Hammadullah3(config-if)#ip add
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/3/0, changed state to up

% Incomplete command.
Hammadullah3(config-if)#ip address 10.10.10.9 255.255.255.252
Hammadullah3(config-if)#clock rate 64000
Hammadullah3(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/3/1, changed state to down
Hammadullah3(config-if)#exit
Hammadullah3(config)#router eigrp 15398
Hammadullah3(config-router)#network 192.168.1.16 0.0.0.7
Hammadullah3(config-router)#network 10.10.10.4 0.0.0.3
Hammadullah3(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.5 (Serial0/3/0) is up: new adjacency

Hammadullah3(config-router)#network 10.10.10.8 0.0.0.3
Hammadullah3(config-router)#no auto-summary
Hammadullah3(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.5 (Serial0/3/0) resync: summary configured

%LINK-5-CHANGED: Interface Serial0/3/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/3/1, changed state to up

%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.10 (Serial0/3/1) is up: new adjacency

%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.10 (Serial0/3/1) is resync: graceful restart
|
```

 Hammadullah98

Physical Config CLI

IOS Comr

```
cisco 2811 (MPC860) processor (revision 0x200) with 60416K/5120K bytes of memory
Processor board ID JAD0S190MTZ (4292891495)
M860 processor: part number 0, mask 49
2 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
239K bytes of non-volatile configuration memory.
62720K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 2800 Software (C2800NM-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 06:21 by pt_rel_team
```

Press RETURN to get started!

```
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#Hostname Hammadullah98
Hammadullah98(config)#int Fa0/0
Hammadullah98(config-if)#ip address 192.168.1.25 255.255.255.248
Hammadullah98(config-if)#no shutdown

Hammadullah98(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah98(config-if)#int Se0/3/0
Hammadullah98(config-if)#ip address 10.10.10.10 255.255.255.252
Hammadullah98(config-if)#no shutdown

Hammadullah98(config-if)#
%LINK-5-CHANGED: Interface Serial0/3/0, changed state to up

Hammadullah98(config-if)#exit
Hammadullah98(config)#router eigrp
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/3/0, changed state to up

% Incomplete command.
Hammadullah98(config)#router eigrp 15398
Hammadullah98(config-router)#network 192.168.1.24 0.0.0.7
Hammadullah98(config-router)#network 10.10.10.8 0.0.0.3
Hammadullah98(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.9 (Serial0/3/0) is up: new adjacency

Hammadullah98(config-router)#no auto-summary
Hammadullah98(config-router)#
%DUAL-5-NBRCHANGE: IP-EIGRP 15398: Neighbor 10.10.10.9 (Serial0/3/0) resync: summary configured
|
```

