




Hammadullah15398-1

Physical Config CLI

Compiled Wed 18-Jul-07 06:21 by pt_rel_team

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>en

Router#config t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#hostname Hammadullah15398

Hammadullah15398(config)#

Hammadullah15398(config)#interface FastEthernet0/0

Hammadullah15398(config-if)#ip address 192.168.1.1 255.255.255.0

Hammadullah15398(config-if)#no shutdown

Hammadullah15398(config-if)#

%LINK-S-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-S-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah15398(config-if)#exit

Hammadullah15398(config)#interface Serial0/3/0

Hammadullah15398(config-if)#clock rate 64000

Hammadullah15398(config-if)#ip address 10.0.0.1 255.0.0.0

Hammadullah15398(config-if)#no ip address

Hammadullah15398(config-if)#no clock rate

Hammadullah15398(config-if)#ip address 10.0.0.1 255.0.0.0

Hammadullah15398(config-if)#ip address 10.0.0.1 255.255.255.252

Hammadullah15398(config-if)#clock rate 64000

Hammadullah15398(config-if)#no shutdown

%LINK-S-CHANGED: Interface Serial0/3/0, changed state to down

Hammadullah15398(config-if)#

%LINK-S-CHANGED: Interface Serial0/3/0, changed state to up

%LINEPROTO-S-UPDOWN: Line protocol on Interface Serial0/3/0, changed state to up

Hammadullah15398(config-if)#exi

Hammadullah15398(config)#router rip

Hammadullah15398(config-router)#version 2

Hammadullah15398(config-router)#network 192.168.1.0

Hammadullah15398(config-router)#network 10.0.0.0

Hammadullah15398(config-router)#no auto-summary

Hammadullah15398(config-router)#exit

Hammadullah15398(config)#

 Hammadullah15398-2

Physical Config CLI

IOS Comm

```
Hammadullah15398(config-if)#ip address 172.16.1.1 255.255.0.0
Hammadullah15398(config-if)#ip address 172.16.1.1 255.255.255.0
Hammadullah15398(config-if)#no shutdown

Hammadullah15398(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Hammadullah15398(config-if)#exit
Hammadullah15398(config)#interface Serial0/3/0
Hammadullah15398(config-if)#ip address 10.0.0.2 255.0.0.0
Hammadullah15398(config-if)#ip address 10.0.0.2 255.255.255.252
Hammadullah15398(config-if)#clock rate 64000
This command applies only to DCE interfaces
Hammadullah15398(config-if)#no shutdown

Hammadullah15398(config-if)#
%LINK-5-CHANGED: Interface Serial0/3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/3/0, changed state to up

Hammadullah15398(config-if)#exit
Hammadullah15398(config)#router rip
Hammadullah15398(config-router)#version 2
^
% Invalid input detected at '^' marker.

Hammadullah15398(config-router)#version 2
Hammadullah15398(config-router)#network 172.16.1.0
Hammadullah15398(config-router)#network 10.0.0.0
Hammadullah15398(config-router)#no auto-summary
Hammadullah15398(config-router)#exit
Hammadullah15398(config)#exit
Hammadullah15398#
%SYS-5-CONFIG_I: Configured from console by console

Hammadullah15398#config t
Enter configuration commands, one per line. End with CNTL/Z.
Hammadullah15398(config)#access-list 101 permit tcp 172.16.1.0 0.0.0.255 host 192.168.1.10 eq 21
Hammadullah15398(config)#access-list 101 permit tcp 172.16.1.0 0.0.0.255 192.168.1.10 eq 20
^
% Invalid input detected at '^' marker.

Hammadullah15398(config)#access-list 101 permit tcp 172.16.1.0 0.0.0.255 host 192.168.1.10 eq 20
Hammadullah15398(config)#access-list 101 deny ip 172.16.1.0 0.0.0.255 host 192.168.1.10
Hammadullah15398(config)#access-list 101 permit ip any any
Hammadullah15398(config)#int Fa0/0
Hammadullah15398(config-if)#ip access-group 101 in
Hammadullah15398(config-if)#exit
Hammadullah15398(config)#
```

Server0

PhysicalConfigServicesDesktopCustom Interface

SERVICES

HTTP

DHCP

DHCPv6

TFTP

DNS

SYSLOG

AAA

NTP

EMAIL

FTP

FTP

Service ☒ On ☐ off

User Setup

Username

Hammad

Password

15398

☒ Write ☒ Read ☒ Delete ☒ Rename ☒ List

	Username	Password	Permission
1	cisco	cisco	RWDNL
2	Hammad	15398	RWDNL

Add

Save

Remove

File

1

asa842-k8.bin

2

c1841-advipservicesk9-mz.124-15.T1.bin


3

c1841-ipbase-mz.123-14.T7.bin

4

c1841-ipbasek9-mz.124-12.bin


Remove



The screenshot shows the Packet Tracer PC3 Desktop environment. A Command Prompt window is open, displaying the following text:

```
Packet Tracer PC Command Line 1.0
PC>ftp 192.168.1.10
Trying to connect...192.168.1.10
Connected to 192.168.1.10
220- Welcome to PT Ftp server
Username:Hammad
331- Username ok, need password
Password:
230- Logged in
(passive mode On)
ftp>dir

Listing /ftp directory from 192.168.1.10:
0   : asa842-k8.bin                               5571584
1   : c1841-advipservicesk9-mz.124-15.T1.bin      33591768
2   : c1841-ipbase-mz.123-14.T7.bin               13832032
3   : c1841-ipbasek9-mz.124-12.bin                16599160
4   : c2600-advipservicesk9-mz.124-15.T1.bin      33591768
5   : c2600-i-mz.122-28.bin                       5571584
6   : c2600-ipbasek9-mz.124-8.bin                 13169700
7   : c2800nm-advipservicesk9-mz.124-15.T1.bin    50938004
8   : c2800nm-advipservicesk9-mz.151-4.M4.bin     33591768
9   : c2800nm-ipbase-mz.123-14.T7.bin            5571584
10  : c2800nm-ipbasek9-mz.124-8.bin               15522644
11  : c2950-i6q412-mz.121-22.EA4.bin             3058048
12  : c2950-i6q412-mz.121-22.EA8.bin             3117390
13  : c2960-lanbase-mz.122-25.FX.bin             4414921
14  : c2960-lanbase-mz.122-25.SF11.bin           4670455
```



The screenshot shows the Packet Tracer PC3 Desktop environment. A Command Prompt window is open, displaying the following text:

```
Packet Tracer PC Command Line 1.0
PC>ping 192.168.1.10

Pinging 192.168.1.10 with 32 bytes of data:

Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 192.168.1.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```