

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

GPIO Mode and Configuration

Configuration

Group By Peripherals

GPIO

I2C

RCC

Search Signals

Search (Ctrl+F)

☐ Show only Modified Pins

Pin N...	Signal on...	GPIO out...	GPIO mo...	GPIO Pul...	Maximum...	User Label	Modified
PA0-WK...	n/a	Low	Output P...	No pull-u...	Low		☒
PA1	n/a	n/a	Input mode	Pull-up	n/a		☒
PA2	n/a	n/a	Input mode	Pull-up	n/a		☒
PA3	n/a	n/a	Input mode	Pull-up	n/a		☒

PA3 Configuration:

GPIO mode

Input mode


GPIO Pull-up/Pull-down

Pull-up

User Label

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

I2C2 Mode and Configuration

Mode

I2C I2C

Configuration

Reset Configuration

☒ NVIC Settings ☒ DMA Settings ☒ GPIO Settings
☒ Parameter Settings ☒ User Constants

Configure the below parameters

Search (Ctrl+F)

Master Features

I2C Speed Mode Standard Mode

I2C Clock Speed (Hz) 100000

Slave Features

Clock No Stretch Mode Disabled

Primary Address Length selection 7-bit


Dual Address Acknowledged Disabled

Primary slave address 0

General Call address detection Disabled

Pinout view

System view





Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Slave Mode

Trigger Source

☒ Internal Clock

Channel1

Channel2

Channel3

Channel4

Combined Channels


Configuration

Reset Configuration

NVIC Settings			
Parameter Settings			
NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Slave Mode	Disable
Trigger Source	Disable
☒ Internal Clock	
Channel1	Disable
Channel2	Disable
Channel3	Disable
Channel4	Disable
Combined Channels	Disable

Configuration

Reset Configuration

☒ User Constants	☒ NVIC Settings	☒ DMA Settings
☒ Parameter Settings		

Configure the below parameters:

Search (Ctrl+F)	
Counter Settings	
Prescaler (PSC - 16 bits value)	7199
Counter Mode	Up
Counter Period (AutoReload Regist.	4999
Internal Clock Division (CKD)	No Division
auto-reload preload	Disable
Trigger Output (TRGO) Parameters	
Master/Slave Mode (MSM bit)	Disable (Trigger input effect not delayed)
Trigger Event Selection	Reset (UG bit from TIMx_EGR)

Pinout view

System view

