Collate

When you turn on the Collate option, InDesign prints the range of pages you've specified, in order, for each copy of the publication you print. This makes for much slower printing. When you print multiple copies of a page, your printer only needs to process each page once (and then prints multiple copies of the page using the same image); when you turn on the Collate option, your printer must process each page once for every copy of the print job.

Reverse Order

When you print a multipage document, do you want the first page to come out first or last? Turning on the Reverse Order check box tells InDesign to print the last page first, then print "backwards" to the first page. You'll want to turn this on if your pages come out of the laser printer face up.

Page Ranges

Turn on the All Pages option to print all of the pages in the publication. To print a range of pages, turn on the Range option. Enter the page range in the Range field as shown in the following Table.

To print	Enter	Example
A continuous range of pages	first page - last page	12-21
Up to a specific page	- last page	-5
From a page to the end of the document	first page -	5-
Non-contiguous pages	page, page	1, 3
Mixed page ranges	page, range	-3, 6-9, 12, 15-
Pages by section	section:page	Sec1:1, Sec2:5

Sequence

To print even and odd pages, select the All Pages option from the Sequence pop-up menu; to print even pages, select Even Pages Only; and to print odd pages select Odd Pages Only. These choices affect all page ranges, including page ranges you've entered in the Range field.

Print Master Pages

Sometimes you need to print your master pages instead of your document pages. No problem: Just turn on the Print Master Pages check box. When you do this, you cannot specify page ranges—InDesign prints all the master pages in the document.

Print Blank Pages

What happens when you print a three-page document that has nothing on page 2? By default, only pages 1 and 3 print out. If you want the blank page 2 to print, too, you'd better turn on the Print Blank Pages check box.

Print

Finally press the Print button to print the document



The Control panel has two buttons that allow you to switch between formatting characters and formatting paragraphs. The two buttons are at the far left side of the panel. The Letter "A" button is the Character Formatting Controls button. Click this button to display options for formatting characters, such as Font Size, Superscript, and All Caps, on the left side of the Control panel. The ¶ button is the Paragraph Formatting Controls button. Click this button to display options for formatting paragraphs, such as alignment and indentation, on the left side of the Control panel.

XII CompTech_English version CHAPTER 02.indd 80 01-03-2020 13:04:37