

executing the following command:
chkconfig -level 35 swat on.

Check if the application has started properly by typing:
chkconfig -list | grep swat.

The result should be 'swat: on'. Once it's verified that the service is running, let's see how it eases the configuration task.

Run the Utility

To start with the Samba configuration, go to the browser, and type **http://localhost:901/** in the location bar.

Next, specify the user name as root and enter the password to start off with the configuration. If you enter the wrong user name or password, it will not give you a second try. If you manage to mess this up, restart the xinetd service, as mentioned above. Use this configuration utility on a remote machine cautiously, since the username and password is sent as simple text (without encryption) across the network.

Configure

When you view the **/etc/samba/smb.conf** file, you will notice that it is organised into sections. Although we won't be directly modifying the files, the GUI tool (SWAT) will modify it. The first section consists of global settings. It defines the server's overall attributes, including the two most important settings: workgroup name, and NetBIOS name.

The next section deals with shared folders. By default, one share is created called 'homes'. This is a private share, and is visible to the users, who use a valid username and password. By this share, users can access their own home folder over the network. To see the details of the homes share, select home from the drop down box, and press Choose Share. To save any changes you make, press the Commit Changes button. To add a new share, type the share's name in the text

box besides the Create Share button, and then, press the Create Share button. Type the folder name you wish to share along with security settings such as 'quest=yes', or 'guest=no', and Commit Changes. You have successfully created a shared folder in Linux that can be accessed even from Windows PCs.


Once the shares are created, check whether the users are configured properly to access the shared folders. To manage




Users have to be given access rights to the shared folders

the users for Samba, go to the Password section. This section is split vertically into two halves. The top half helps in managing Samba users on the local machine, while the bottom half helps in changing the password on the remote Windows PC. The username and password on the local and remote machine should be the same. Before adding a Samba user in the Server Password Management, check if the users are present on the local machine. If not, then add users in the local machine first. Samba has a limitation that only allows users with a valid local account to access the shares.

Sharing printers is very similar to sharing folders. It works for major Linux print services such as LPD (Line Print



Sharing printers is very similar to sharing folders, using SWAT



SWAT lets you share folders with ease

Bonus TIP 2

Set your display properties easily


On earlier Linux versions, the only way to get your GUI working, was to use Xconfigurator—a console-based utility that acted as a rudimentary front-end to the X server's configuration file. But now, a new tool, called **redhat-config-xfree86**, has been included that makes changing display properties very similar to that in Microsoft Windows. To start the tool, go to the **Main menu > System Settings > Display**. Alternatively, you could execute the command: **redhat-config-xfree86**.



Adjust colour and resolution easily

In the window that pops up, you can change the resolution, as well as colour depth. Press OK, and that's it.

You can also change the hardware drivers for your monitor, or graphics card, using this utility. When the utility opens, go to the Advanced tab. Here, you can configure both, the monitor and the graphics card. Click the configure button, to get a list of supported drivers. Choose one from the list, or use the Probe button



Configure the monitor via the Advanced tab

to detect the hardware. Once you have chosen the proper hardware, press OK.

Once you change any display settings, you need to restart your X server for the changes to take effect. This can be done by simply logging out, and starting a new session again.