

Digital Tools | Tips & Tricks

Premiere Shortcuts

Tool shortcuts

Track Select tool	[A]
Ripple Edit tool	[B]
Razor tool	[C]
Hand tool	[H]
Rolling Edit tool	[N]
Slide tool	[U]
Selection tool	[V]
Rate stretch tool	[X]
Slip tool	[Y]
Zoom tool	[Z]

Panel shortcuts

Project panel	[SHIFT]+[1]
Source Monitor	[SHIFT]+[2]
Timeline panel	[SHIFT]+[3]
Program Monitor	[SHIFT]+[4]
Effects controls	[SHIFT]+[5]
Audio Mixer	[SHIFT]+[6]
Effects panel	[SHIFT]+[7]

Timeline shortcuts

Nudge 5 frames right	[ALT]+[SHIFT]+[.]
Nudge 5 frames left	[ALT]+[SHIFT]+[,]
Nudge 1 frame right	[ALT]+[.]
Nudge 1 frame left	[ALT]+[,]
Toggle play/stop	[SPACEBAR]
Play forward slowly	[K]+[L]
Play backward slowly	[K]+[J]
Shuttle left	[J]
Shuttle right	[L]
Ripple delete	[ALT]+[BACKSPACE]
Set in point	[I]
Set out point	[O]
Trim	[T]

Capture shortcuts

Record	[G]
Stop	[S]
Go to in point	[Q]
Go to out point	[W]




Blank Video

To add blank video to the project, right-click in the bin, go to **New Item > Black Video** and select **OK**. This is basically a black matte that can be used at the beginning or at the end of the film, and by default it lasts for six seconds. To use a matte in any other color, right-click in the bin, go to **New Item > Color Matte**. A color picker will appear, choose a color or enter the values and click **OK**. This too, by default lasts for six seconds. To change this default setting, go to **Edit > Preferences > General** and change the 'still image duration' value. 150 frames is equal to six seconds, so if you want twelve seconds, change the value to 300.



Change Playback Speed

There are many ways to change the speed at which a clip plays back. To change the speed consistently across all the edits in the timeline, right-click on the video in the bin, select **Speed / Duration** in the context menu, and change the speed value from 100% to whatever you want. Alternatively, you can change the duration




Changing the speed/duration in premiere

value and make the clip last exactly so many seconds. If however, you want to change the speed of only a small portion of the clip in the timeline, use the razor tool to cut out that part of the clip, and right-click to bring up the context menu, then select **Speed / Duration**. Checking the **Reverse Speed** option will play the clip backwards.



A-V Links

Whenever a clip is added to the sequence, it gets split into two parts. The audio part shows up in an audio track, and the video part shows up in the video



Syncing unlinked Audio and Video components

track. When you move them, or cut them, the changes that affect one also affect the other. This occurs because the two are linked to each other. You can find out if media is linked by looking at their title. If they are linked, the title will be underlined followed by a [A] annotation for audio and a [V] annotation for video. To perform any operations on them separately, right-click on the clip and select 'Unlink'. It is possible to synchronize operations on an audio and video sequence that you want to link up together. To do this, align the audio and video sequence together on the timeline, select both of them, right-click and click **Link**. If either the audio or the video track is askew at this point—they will remain so through further edits unless you correct them. Moreover, premiere keeps track of unlinked audio and video components of the same file, so you can relink them if there is any need. Select the unlinked components, right-click, and select **link**. If they are askew, Premiere shows up the duration by which the synchronization is off in red numbers on a white box to the left of the title. Right-click on this box and 'select move into sync' to rectify the synchronization error automatically.



Docking Panels

You can move most of the panels around the workplace. The default editing view has a number of tabbed panels arranged in 6 areas. When you move around a panel from one place to another, just before you dock it, a purple highlight indicates the position where it is going to be docked. Whenever you move a panel to another position, if the highlight is on the middle of the panel, then it will be added as a tab. If the top, bottom, left or right one-third of the panel gets highlighted, then the two panels will share the space, and dock next to each other in the positions indicated. If the highlight appears on the title bar, then the panel is going to be docked as a tab.