




tips & tricks

Keep yourself free
Take part in the Digit
Carnival coming your way

28

Ripping



to manually write the info. Click on Edit Track and Edit Album Info buttons or right-click on the track. Once this is done you can click Start Ripping. You will be able to choose the file type you want to rip to (FLAC, Ogg, or Mp3). In the file naming tab you can choose the way in which the ripped files are named. You can insert %g in the string to have the genre included in the file names. You can then click on Start Ripping to extract audio.

Slow down the read speed


K3b allows you to slow down the read speed so that the annoying high pitched noise reduces while reading CDs. Click on Device > Set Read Speed and specify the speed you want. This speed will be set for the currently mounted drive.

Change read speed

Please enter the preferred read speed for **HL-DT-ST DVD-RAM GH22N530**. This speed will be used for the currently mounted medium.

This is especially useful to slow down the drive when watching movies which are read directly from the drive and the spinning noise is intrusive.


Be aware that this has no influence on K3b since it will change the reading speed again when copying CDs or DVDs.



DVD Image Burning

K3b allows you to burn iso images onto DVD media. Click on Tools > Burn DVD ISO Image. You can then point to the ISO image file that you wish to burn and the burner will do the rest.

Writing Audio CD in K3b.png




Overburn

Overburning is a way to burn a little bit of extra data which is beyond the specified capacity of the media. If you have a 700 MB disk and wish to burn that little extra 4 MB song on it, you can. Click on Settings > Configure K3b. Go to the Advanced options and check Allow Overburning.

No Eject after burning

Sometimes it gets very annoying when writing applications pop the disk out after the burning process is over. K3b allows you to choose to not eject the medium. Go to Settings > Configure > Advanced. Under Miscellaneous, uncheck the box for 'Do not eject medium after write process'.



Change look

As with most applications, you can change the feel of K3b. It allows for themes to be changed to change the look of the software. To change theme, go to Settings > Configure > Themes. Here, you will find a few themes that come bundled. Click on any theme and click Apply. You can also install new themes. Click on the Install New Theme button and point to the theme file. You can search online for themes.


Saving all projects

Sometimes burning a DVD can be quite a process which can last multiple sessions. In fact, since K3b allows you to work on more than one project (in tabbed form) it can be even more time consuming. In such a case, you can choose to save all the projects that you're currently working on. To save all the projects, click on File > Save All. You will then be prompted to assign project names to each of the tabs and save them.

Split audio tracks

K3b allows you to split audio tracks while burning audio CDs. Simply right-

Split Audio Tracks



click on the track in the current project and click split tracks. You will get a slider to choose the splitting position, or you can specify the new timings of the split tracks (e.g. 00:00:59 - 00:02:12).


Make a data CD for Linux, Windows or both.

A data CD is a optical disk that is formatted to store data in the form of files. The files typically stored on a Data CD include MP3 audio, documents, compressed archives, and even Linux packages. With K3b, you can write a data CD that can be read on both Windows as well as Linux Machines. To make a data CD in K3b, click on File > New Project > New Data CD Project or you can click on the New Data CD icon in the quick start menu. You can rename the volume by entering a name on the top right corner above the contents of the project. Click on Project > Add Files to open the dialog box to add files. You can drag and drop or select multiple files and click Open. Once you are done adding files, click on Burn to initiate the burning process. In the new dialog box, click on the File System Tab. In the drop down menu choose the appropriate option (Linux/Unix + Windows or Linux/Unix only). Click on Burn when ready.

Make a mixed mode CD

A disk with a data track as well as an audio track is a mixed mode CD. Therefore, you can effectively combine two data types (files and playable audio). Such CDs can be played on a Hi-Fi system and the data track can be read on a computer. To make a mixed mode CD click on File > New Project > New Mixed Mode CD Project.

Mixed Mode CD



In the adding menu, you will find an audio track and a data track section. Select one of them before adding files. When you add an MP3 file to the data track, it will be stored as data if the selection is on data track. If it is on audio, it will be converted to CD audio.

Click on Burn when done. In the new Dialog box, click on the Misc tab. Here, you can choose if you want the data track or the audio to be the first track on the CD. Typically, the Data Track is the first track.