




Select Custom Dependencies from the Quad Menu

Decreasing render time

One of the most common things you do when building complex poly models is keep rendering the image to keep testing for the final outcome. It is very important to lower the time it takes for the test render to speed up the testing process and the general workflow.

1) We first need to reduce the size of the image that needs to be rendered. It is recommended you use a 150x110 pixel size output. Although this may not let you see the details of the object, it is good to test lighting conditions and shadows in the

final output.

2) Decreasing the quality of the shadow will speed up the render time significantly.

3) Decreasing the number of polygons in the object also speeds up your render time. You can try and use the optimize modifier if you are not using any mesh modifier on the objects.

4) You can also reduce the photon number and the settings for “sample” in the render

engine options.

5) Make sure you haven't used excessive lights where they are not necessary. Higher the number of lights, the slower the process of rendering is.

Light and Shadows

1) Generally architectural

materials and self-illuminated materials are light emitting for rendering engines like Mental Ray & Vray. Using these particular materials on an object like a box will have the same effect as that of a photometric area light or a Vray light.

2) Always make sure you are using soft shadows in most common cases before rendering. Hard shadows have a tendency of making the object and the final image appear fake. You can change the settings on the Mr Omni / Spot scale by changing the size of the light in the area light parameters. For rendering using Mental Ray you will have to make use of RAYTRACED shadows. For Vray just enable

for Mental Ray. The best and usually the quickest way for obtaining effective results are by using the Raytrace shadows. In case you are working with the ‘light tracer’ and use ‘area shadows’ the result should ideally be the same as that of MentalRay with Raytrace shadows.

Mesh and Polygons

1) It is always good to use an ‘editable poly’ rather than a Mesh. An Editable Poly is optimized and required for any advanced modelling. Using an editable poly has a lesser scope of you committing errors than working with an editable mesh and an editable poly has way more options than you would get with an editable mesh. Even

if you are working on an object with an editable mesh it is very easy to convert it into an editable poly object.


2) Instead of smoothing a box with mesh smooth, you can make use of “extended primitives” or a “chamfer box”, the result of which will be the same. But note that the chamfer box has lesser polygons.

3) Instead of using mesh smooth you can also simply use the built in nurms feature

for the editable poly. Just bind a hot key to the “NURMSToggle - Poly” option and you should be



Render Preferences



Render Setup

‘area shadow’ in the Omni / Spot settings and change the size of the light. But note that in general, soft shadows take more time to render. To have perfect shadows it is necessary to create all objects with real dimensions.

3) To get the best highlights and effects on highlights Omni light or MR Omni is the most preferred light.

4) Make sure to never use any area shadows while rendering with Mental Ray since area shadows are firstly very slow and also they are not optimized



Mesh vs. Poly