




Use Adjust Variations dialog to colorize Black and White Photos.

specific areas to finalise the image.

Print easy

The easiest way to print your images is to use the Photo Printing Wizard in Windows XP. Open the image folder in Windows Explorer, select the images you need to print while holding down [Ctrl] and then click 'Print the selected pictures' under Pic-



Print your images easily with Windows XP's Photo Printing Wizard

ture Tasks. Follow the instructions to print your images in Full Page, Contact Sheet, 8 x 10, 5 x 7, 4 x 6, 3.5 x 5 or Wallet prints.


File naming

By default, images downloaded from a digital camera are named as DSCN0001, DSCN0002, ... Use the batch function in Windows XP to rename them. Open the image folder in Windows Explorer, hold down [Ctrl], select all the desired images and press [F2]. Name them appropriately and press [Enter]. If you entered 'birthday', the last selected file will be renamed 'birthday' and the preceding files will be renamed 'birthday (1)', 'birthday (2)', etc.

Photos on the Web

Windows XP's Web Publishing Wizard stores photographs online, as private or public albums. Open the folder that contains your photographs, hold down [Ctrl] and select the pictures you want to share. Next, click 'Publish the selected items to the Web' under 'File and Folder Tasks' to start the Wizard. After you have confirmed the photos you want uploaded, specify its location to the Service Providers in the next screen. Here,

we choose MSN Groups—the standard option. The wizard then gives you the option of keeping your files public or private. Accordingly, you are asked the name of the group



Use Windows XP's Web Publishing Wizard to share your photos easily

and a few other details as part of the registration process. It then displays the Web address of your group. Finally, the Wizard uploads the photos.

E-mailing

To e-mail photographs, right-click the image in Windows Explorer and choose **Send To > Mail Recipient**. A dialog box in Windows XP provides you with three options to re-size the image prior to e-mailing it: 640 x 480 strictly for computer viewing, 800 x 600 for 4 x 6 prints and 1024 x 768 for 5 x 7 prints. Of course, you can always send it as it is!


Histogram

Exposure is one important factor that differentiates good photos from shoddy ones. A good photo has all its elements illuminated properly. Use the histogram to correct exposure. Though many cameras show a histogram on their LCDs after you take a picture, it's better to view the histogram in a photo-editing tool and make corrections there. Access the

histogram in Photoshop by going to **Image > Adjustments > Levels**.

The right side of the histogram shows the lightest portion or 'highlights' of the images, the middle section shows the mid-tones and the left most side shows the darker portions

or 'shadows'. The vertical axis shows the pixels in each



Use Histogram to correct the exposure in your photographs

level. An underexposed image has many pixels concentrated in the shadows. Move the sliders to improve the distribution of brightness levels. Alternatively, use the Auto button to let Photoshop make the adjustments. Further, you can also adjust histogram of channels, i.e red, blue and green, if their distribution appears improper. For example, adjust the histogram for the blue channel if the sky looks dull in your photograph ■