

Bonus Tip

Specific Uses

Don't edit video files in either Adobe Audition or Sony Sound Forge. Audio editing software are not made for video editing, and to do so professionally, you should use specialised software such as Adobe Premiere Pro.

Sound Forge

Go to "Effects > Flange/Wah-wah...". A box pops up which will have three radio buttons, one each for Flange, Phaser and Wah-Wah. Select the effect you want, set the rate, depth, resonance and frequency of the effect and then preview your sound. Use the Real-time preview monitor to make changes.

Audition

Audition offers a Flange effect, and a Sweeping Phaser effect. These are accessible from the "Effects > Delay Effects" menu. Audition does not offer a Wah-Wah effect. Use the preview and bypass functions to check and re-check your settings.

Inserting Silence



When compiling a CD, or preparing a track for

mixing, you may need to insert a predefined period of silence. This will let audio CD players distinguish between tracks or give you the correct spacing that is required when mixing two tracks.

Sound Forge

To insert silence in Sound Forge, go to "Process > Insert Silence...". Add in the length of the silence you want to add, choose to add it at either the position the cursor is, or at the beginning or end of the

track, and click OK.


Audition

In Audition, go to "Generate > Silence", and enter the number of seconds, and press OK.


Converting Between Mono And Stereo



Sometimes, you may need to convert a track that was recorded in mono to stereo. Rarely would you need to convert stereo to mono, though this is also possible. Both software have



Convert your tracks between mono and stereo easily, in order to better control your dual channel output



an easy way of converting between mono and stereo to give you control over your dual channel output.

Sound Forge

In Sound Forge, just right-click anywhere and select Properties. Click on the Format tab to see file options. Here you can change the Sample rate, Bit-depth, and the Channels (Mono and Stereo). Just select Mono or Stereo, depending on which way you are converting, and click OK. When converting from mono to stereo, a box will pop up, asking you whether you want to convert to mono using only the left track, the right track, or to mix both tracks (standard). This can also be used to separate left and right tracks, to save them as separate mono files. Now use 'Save As...' to save the file with a new filename-for example, track1.mp3 can be saved as mono-left_only-track1.mp3.

Audition

To convert between mono and stereo, go to "Edit > Convert Sample Type...", or press [F11]. Here you can choose the Sample Rate, Channels (stereo or mono), and the Resolution (bit rate). Make the appropriate selections and then either save as a new file or just press OK to overwrite the existing file. When converting between mono

Jargon Buster

Flanger: A Flanger basically applies a variable delay in real time to sound, creating a swirling, windy effect. Blow out air from your mouth, and shape your lips the way you say "O". Continue to blow air and change the shape of your lips to the way you say "E". The change in the pitch of the sounds is similar to what the Flanger does.

Phaser: The Phaser effect is very similar to the Flanger effect, but instead of using just delay, it overlays an out of phase copy of a sound onto the same sound. This causes it to make a "swooshing" windy sound.

Wah-wah: If you make a constant sound with your

mouth, and then alternatively cover and uncover your mouth with your hand, you will get the effect of a Wah-wah. This effect, also known as the cry-baby effect, is reproduced electronically by increasing and decreasing the harmonics of a sound.

Harmonics: Multiples of a given wave's frequency. For example, a 100 Hz sound will have 200 Hz, 400 Hz, 600 Hz, etc., as even harmonics, and 300 Hz, 500 Hz, 700 Hz, etc. as odd harmonics.

Pitch: The basic frequency of a sound. Higher and Lower pitches are associated with treble and bass respectively.

Pitch-shifter: An effect that

increases or decreases the pitch of a sound in harmonic steps.

Tempo: Measured in beats per minute, it symbolises the speed of a song.

Crossover: A crossover is a frequency filter that filters high, low and mid range frequencies and sends them to the tweeters, woofers and mid speakers respectively.

Tweeters: Generally a small cone that outputs sound of the highest frequencies.

Woofers: Dynamic cone speakers that output bass (low frequency) sounds.

Subwoofer: This is a device that plays sounds of 120 Hz and less. It produces bass with 'punch', especially at high volumes.