

Browse the web via SMS

Cosmos for Android app wants to let its users access the web via text messages by only filling in the URL. <http://dgit.in/CosmosAndroid>

**Airbus' patented helmet**

Airbus is building a helmet display, which they are patenting, to isolate you from your fellow passengers. Read more here: <http://dgit.in/AirbusHelmet>

A not so Powerful Nexus

When your trusty old Nexus device's power button starts acting up, what do you do? One of the following things.

Jayesh Shinde
jayesh.shinde@digit.in

A darling among Google's Nexus lineup of devices, one that actually created waves by selling at an atrociously low unlocked price in the US (where people are only ever used to buying phones with a contract with telcos). The Nexus 4 handset is just shy of being two years old now. A lot of Indians sport the popular Google phone simply because it was the first one to be sold officially in hither shores. Apart from one small problem which has been experienced by a substantial number of Nexus 4 – and to some extent Nexus 7 tablet – owners.

You see, the power button of the Nexus 4 isn't its most shining part. In fact, it's not only difficult to press, but it allegedly worsens as time goes on. There are a number problems plaguing the Nexus 4's hardware buttons, and we've experienced most of them progressively over the past two years. So here's what we've found you can do to either alleviate the pain by having to deal with a constantly dysfunctional power button on the trusty old Nexus 4.

What's the problem?

Nexus 4's power button unleashes several pain points in end user experience, particularly as the device gets older. We've

heard (and to some extent experienced ourselves) people complaining about the following on their Nexus 4 smartphone and Nexus tablet with respect to its power button:

- That it becomes harder to press as the device ages. What used to take a single click earlier now takes two, three or even more repeated presses for either locking or unlocking the device.
- The phone is late to acknowledge the triggers of the power button, leading to a scenario where you repeatedly press the power button multiple times only for the device to lock and unlock immediately (or vice versa).
- Long pressing the power button also becomes a hit-n-miss affair as time goes along.
- All of these power button issues are compounded even more if you're prone to using your Nexus 4 phone (or Nexus 7 tablet) in a case, since it makes it that much more harder to hit the power button accurately and requires greater force.

Granted, every device goes through mechanical




wear and tear, and the Nexus devices aren't immune to this gradual degradation of hardware parts. However, the power button's behaviour isn't clear cut to suggest that.

Boot into safe mode

More often than not, it's usually an app that sends your phone's software into a tizzy. If you sense that the power button was fine until a software update or app installation, then try to see if your hunch is correct. And just like you would on your

Windows PC, the Nexus 4 also allows you to boot into safe mode to see if everything is working hunky dory or not. You can start up your device in safe mode, which temporarily disables third-party apps that you've installed.

- Ensure your device's screen is on, then press & hold the Power button.
- Touch and hold the Power off option in the dialog box.
- Touch OK in the following dialog to boot into safe mode.



Reboot to safe mode dialog.