




The GeeXboX controls

through GeeXboX's menus unlike any other software available.

It is also possible to play back network streams from SHOUTcast, WebRadios, WebTVs or even RTP/RTSP streaming allowing you to watch any kind of network or broadcast stream from your own GeeXboX hub.

### Get Going!

Setting up the system is not a difficult task at all. The following sections discuss the essentials.

### Reload The Ammo

Officially, GeeXboX requires at least a x86 Pentium-Class CPU or above (P2-400 MHz should be quite enough) or Macintosh NewWorld G3 (G4 highly recommended). However, we found that it sustains fine even on a 300 MHz Zenith PC. The DivX video format is known to cause some genuine hiccups on the oldies though. 64 MB of RAM is generally recommended.


### Fire!

Follow these steps to kick-start a fully functional system in almost no time.

### Running off a live CD

- ❑ Download the GeeXboX ISO image file from [www.geebox.org](http://www.geebox.org) (Listed under downloads section). Next, burn the image, preferably to a Re-Writable CD, as you might want to add/remove features later. This can be done using your favorite CD toaster.
- ❑ Reboot the computer and enter the BIOS setup (Generally, press [Delete], [F8] etc. key after you restart). Change the boot order priority to boot from CDRW/RW drive making it the first.

- ❑ GeeXboX will automatically detect most hardware and auto-mount your partitions.
- ❑ If everything works out fine, you should see a progress bar followed by a graphical boot screen. This will bring you to a menu that displays various options. (If it leaves you at a # prompt then something has failed; more on that later)



Menu items

- ❑ Don't get alarmed when the CD drive's tray pops out after booting. This drive is now free and can be used for playing your own media.
- ❑ The keyboard can be used for navigation. The right arrow key is for moving forward and the left for back. Hitting [Esc] first and then pressing the down arrow key brings one back to the main menu. It is highly recommended that you exercise the *Help* option or keep a printout of the control key diagram as exhibited on the website under the Keys & Controls section.
- ❑ If you choose 'Open File' from the main menu, the media devices and partitions are listed. Navigate to the directory where your goodies are stored and hit the right arrow key to start playing.



Playing a movie

### Troubleshooting Tips

If a flickering black screen greets you right after the boot screen, your video chipset is not yet supported or the config files require a hack or two. This was a known problem with relatively newer Intel motherboards, but the problems were more or less fixed in the last release. The GeeXboX forum on the Web site addresses several such issues and the developers are always keen on increasing hardware support. If compatibility problems do occur, feel free to share information about your device. The response time is generally good and the open source community will do all they can to help you.

### Hack it!

The vanilla ISO image you just ran may not showcase the best features of the system. It may not even run natively without a few hacks on some systems. The following guidelines will demonstrate how you can customize GeeXboX to suit your needs or to recover from a futile attempt at running it.

- ❑ Get the GeeXboX ISO GENERATOR (not the earlier ISO) from the Web site. Uncompress