





Change the IE temporary files location

to the new locations, for example, Storage Card\Internet Explorer 6\ (History, Cookies, Temporary Internet Files)

Improve The Camera's Frame Rate

The frame rate of the camera on your device is limited to around 10 fps. You can take the frame rate up to around 19 fps, which will result in smoother videos. To do this, browse to the key HKEY_LOCAL_MACHINE > Software > HTC > Camera > RecParam > MP4Large. You can choose MP4Medium or



You can change the frame rate of the camera

MP4Small for the other resolutions. Change the value of FrameRate to 19 or any frame rate in between.

Alter Battery Low Warning

When the battery charge level reaches around 10 per cent, your pocket device starts alerting you. To be able to alter any settings or the way you are alerted, start the Registry Editor and browse to HKEY_CURRENT_USER > ControlPanel > Notifications > {A877D663-239C-47a7-9304-0D347F580408}. Create a new string "Default". Change its value: Default="Low battery warning". Now go to Settings > Personal > Sounds & Notifications. Tap on Notifications. Under the Even drop-down menu, click on "Low battery warning", and you can set a range of alerts.

Disable 3GP Video Recording Limitation

3GP video recordings are limited to a particular size. This limitation can be removed by changing a setting in the

Registry. Browse to HKEY_LOCAL_MACHINE > Software > HTC > Camera > AppDefSettings > P3 > EnableLimit. Making the value 0 will disable the limit. Making it 1 again will enforce the limit.

Enable Time In All Applications

The time on the Taskbar can be displayed on the Today window or across all applications. This can be enabled by going to Start > Settings > System > Clock & Alarms. Uncheck the box to disable it, and check it to enable the displaying of time in all applications.


Closing Applications

When you click the OK button in Windows Mobile, it really doesn't shut the program, but in a way makes it inactive. To really shut the program down, go to Start > Settings > System > Memory > Running Programs. Here, you will see the list of programs running. You can choose to shut all of them or select a few individual ones. Clicking a particular program and tapping Activate will make the program active and display it on screen.

Internet Explorer 6?

You can identify your Pocket Internet Explorer as Internet Explorer 6 to sites on the Internet to give you the non-mobile versions.

Browse to HKEY_LOCAL_MACHINE > SOFTWARE > Microsoft > Windows > CurrentVersion > Internet Settings > 5.0 > User Agent. Change the value of Default from Mozilla/2.0 to Mozilla/4.0. Next change the value of Version from MSIE 3.02 to MSIE 6.0. Finally change the value of Platform from Windows CE to Windows NT 5.1.



Identify your browser to sites as IE6

Improve Performance

You can get some additional performance from your devices by changing the cache size.

Browse to HKEY_LOCAL_MACHINE > System > StorageManager > FATFS. Change the value of CacheSize from 0 to 4096. Make sure EnableCache has its value set to 1. In HKEY_LOCAL_MACHINE > System > Filters > fsreplxfilt, set the value of

ReplStoreCacheSize to 4096. A soft reset will be required after this.

Disable Menu Animations

You can do this to cut down on reaction time. Browse to HKEY_LOCAL_MACHINE > System > GWE > Menu. Change the value of AniType from 6 to 0 to completely disable menu animation.

Scrolling In IE

Using a stylus to scroll can be cumbersome over long periods. Using the navigation buttons is relatively comfortable. Navigate to HKEY_LOCAL_MACHINE > SOFTWARE > Microsoft > Internet Explorer > Navigation. Change the value of 4-Way Nav from 1 to 0.

Change The Operator Logo

To change the graphical logo of the phone provider to one of your choice, create a GIF file and place it in the \WINDOWS folder with the name Carrierlogo.gif. The resolution of the image should be around 120x20 to avoid stretching or deformation.

Modify Scrollbar Thickness

A compact device such as a pocket PC or smartphone only has so much space it can spare, so reducing the thickness of scrollbars can help get a little more workspace. Start your Registry Editor and make your way to HKEY_LOCAL_MACHINE > System > GWE. Alter the values of cyHScr (horizontal scrollbar) and cxVScr (vertical scrollbar) to the size of your choice.

Similarly, you can also change the size of the scrollbar arrow buttons. Browse to HKEY_LOCAL_MACHINE > System > GWE. Change the values of cyVScr (the horizon scrollbar button) and cxHScr (the vertical scrollbar button) to a smaller size.

Keypad Backlight Timing

In devices with keypads, a backlight automatically turns on if it is used. The time the light remains on can be changed by going to HKEY_CURRENT_USER > ControlPanel > Backlight. The default value of QKeyLedTimeout is 6; change it to the time you want the backlight to stay on.

Where To Install?

By default, Windows Mobile installs programs on the local memory. If you wish to be able to specify where the program is to be installed, using the Registry Editor, go to HKEY_CLASSES_ROOT > cabfile > Shell > Open > Command. Alter the value of "Default" to wceload.exe "%1" /askdest.

By removing the /nodelete parameter, Windows Mobile will delete the cab after being installed. ☐