


default video player, then click on View > Options. Click Formats and from the list, choose the formats you want Media Player Classic to play for you. If you want all videos to be played in MPC, click the Video button to the bottom right. Click OK.

Fixing Audio Delay

Sometimes we come across videos with some delay in audio playback. With High Definition focussed codec's like H.264, the lower end machines are unable to cope, and a lot of audio delay might be noticed. To compensate this delay, click on View > Options. Click on Internal Filters > Audio Switcher. Enter a value for Audio



Fixing audio playback delay doesn't need you to have media authoring tools


Shift in ms (milliseconds). Enter a positive value to have the audio delayed or a negative value to have the video delayed. Click OK.

Boosting Audio

If the audio in a video isn't loud enough even after increasing all the Windows volume control sliders to the max, you can have Media Player Classic boost it even further. Click on View > Options. Click on Internal Filters > Audio Switcher. Drag the boost slider to increase the volume. Be aware that these changes can create very drastic changes in the volume so be cautious while setting the amount of amplification. Playing back any media with normal amount of amplification might result in very loud audio.

Control From A Web Interface

Media Player Classic has inbuilt components that allow you to use a remote control or even remote access it through a Web browser. For Web-based remote access go to View > Options > Player > Web Interface. Click on Listen on port to enable it. You can change the port as well if you want something easier to remember. Now from a remote PC or even if you have a mobile phone with access to your PC,



MPC can be remotely accessed even through a mobile phone

access [http://YOUR.MACHINE . IP:13579](http://YOUR.MACHINE.IP:13579) (or whatever port you set) through a web browser. A couple of alternate Web interface links can also be used that are present on that page.

If you access MPC using a remote, under Options click on Keys and check the box for WinLIRC and uICE—you may require a compliant remote control though.

Saving Screenshots

Ever had a moment on video that you would love to capture but never knew how—[Print Screen] almost always results in

a black screen. MPC allows you to capture single screenshots by clicking on File > Save Image. Select from BMP or JPG, enter a file name and click Save. If you want thumbnails from the entire video clip, click File > Save Thumbnails. Enter a filename and the number of rows and columns you want. Click Save. An image sheet with the thumbnails and information on the video file will be saved.

Modes


When you aren't watching a video in full screen mode, you can have it running as a window on one corner of your screen. Pressing [2] disables the playback progress bar. The best thing to do if you want a video playing back while you're doing something else—say browsing or chatting is to press [1]. This disables all the title and menus bars and only shows the video. Move the window to the position of your choice and press [Ctrl] + [T]. This puts the MPC window on top of all other applications. If the window is too big in size, press [Alt] + [1] / [2] / [3] / [4] for different preset sizes. You can also set a custom size by clicking and dragging the edges of the window. Pressing [3] brings back the default MPC layout and [Ctrl] + [T] again will disable the On Top mode.

Playlist

When you're viewing more than one video, you would want to be to queue up videos. Press [Ctrl] + [7] to enable the playlist or click on View > Playlist. Drag and drop videos from your folders into this window. While watching a video, pressing [Page Up] loads the next video in the playlist. [Page Down] does the opposite.

Subtitles

Media Player Classic has supported subtitles for quite a while now. However, there are a few changes to the renderer that need to be done before you can actually view them. Click on View > Options. Choose DirectShow VMR7 or VMR9 (renderless). Click OK and restart Media Player Classic. Now open the movie you want to watch. Click on File > Load



Subtitles can be downloaded and viewed through Media Player Classic

Subtitle and point it to the subtitle file you have downloaded. Start the movie and the subtitles will be displayed.

You can customise the way the subtitles are rendered. Go to View > Options > Subtitles > Default Style. Here you can set the subtitles settings such as the position, font, colour, transparency, etc.

Quick Shortcuts

Play/Pause	Spacebar
Stop	.
Volume Up	Up arrow
Volume Down	Down arrow
Full Screen	Alt + Enter
Mute	Ctrl + M
Boss key	B
Zoom In	Numpad 9 (Page Up)
Zoom Out	Numpad 1 (End)
Increase Width	Numpad 6
Decrease Width	Numpad 4
Increase Height	Numpad 8
Decrease Height	Numpad 2
Center view	Ctrl + Numpad 5