



SECRETS THAT KEEP YOU AHEAD IN THE RACE

TIPS

Burning Software 83
 Google Services 87
 Comodo Firewall 90

30 MINUTES EXPERT

XP Secrets 86
 Norton Ghost 88

BURNING SOFTWARE

CDBurnerXP

We burn CDs and DVDs all the time, and Nero's all-too-well-known suite isn't the only option. CDBurnerXP is a free alternative




Harsho Mohan Chatteraj

to Nero, if you don't want to cough up for Nero's features.

Using The Dropbox

The dropbox feature allows you to browse through your Windows folders and dump the items you want to burn. This way, you don't need to browse using the CDBurnerXP interface. To use the feature, click the Show Dropbox button on the toolbar or go to View > Show Dropbox. Drag and drop files onto the box that appears at the top left



The dropbox makes it easier to compile data for a burn

of the screen. The dropbox shows the size of the compilation and the current path where the folders are being dumped. Right-click on it and click Select Folder To Drop Into. This way you can choose which folder the files get dumped. To get back to the default interface, click the Close button on the dropbox.

Set Media Size Manually

Optical disc burning software generally detects the media inserted in the drive and determines the amount of data that can go on it, but you won't get accurate information if you're piling up for a future burn with no disc in the drive. To tell the software the type and capacity of the media, right-click on the



Set the type of media so you know in advance how much space there is

bar for data being burnt and click Select media size. Choose the type of the media you'll be using. The changes will be seen immediately in the main program as well as in the dropbox.




CDBurnerXP houses a basic cover printing feature!

Printing CD Covers

CDBurnerXP might be a fraction of the size of Nero, but it's still got basic features like printing CD covers. Once you have all your data in place for burning, go to File > Print cover and select the type of cover. Enter the name of your disc, and if you want to, choose an image for the cover. Select Preview to see how it'll turn out. If you're happy with it, press Print.

File Filter

The file filter feature allows you to filter out file types that you don't want to burn. For example, if you want to burn all the PDFs in a folder and none of the Excel or Word documents, you will find the feature useful. Click on Edit > File Filter. Enter the file formats that you want to filter with a semicolon to separate them. For example, *.pdf;*.doc;*.xls will only display the PDF, DOC, and XLS formats.



Let CDBurnerXP automatically label discs for you

Disc Labelling Data Options

Most of the time, all the CDs and DVDs you burn end up with the same old senseless label—DISC or DISC1. CDBurnerXP can change this. Go to File > Options > Data Options tab. Under Default Disc Label, enter DVD \$day \$month \$year. There are other variables like \$time, \$user and \$date that you can use as well. Click OK and then restart the program for the changes to take effect.