

**mount /dev/hd xx
mount point**

Here, “xx” stands for the characters that must be substituted, according to the hard disk connection. “Mount point” refers to the directory where you want the partition to be mounted. Linux has a separate directory for this purpose, called *mnt*.

If you want to mount the second partition (as seen by *fdisk -l*), your command is:

mount/dev/hda2/mnt/dir1

This is assuming there is a directory by the name *dir1* in the */mnt* directory. Else you can create one using the *mkdir* command.

2.5.2 Changing the password

In the terminal window (obtained as explained earlier), to change your password, just type in “*passwd newpassword*” where “*newpassword*” is the password you want to use. You will then need to enter your old password.

If you are logged in as the root, type “*passwd <username>*”, where “*username*” is the user name for which you wish the change the password. Upon hitting [Enter], you will be prompted for a new password. You will not be prompted to enter the old password, nor will it be echoed (displayed) to you.

To change the passwords in the GUI, you will need to do some trial and

```
root@test3:~# mount /dev/hda5 /mnt/C
[root@test3 ~]# fdisk -l

Disk /dev/hda: 40,0 GB, 40020684320 bytes
255 heads, 63 sectors/track, 4885 cylinders
Units = cylinders of 16065 * 512 = 8225280 bytes

   Device Boot      Start         End      Blocks   Id  System
/dev/hda1 *          1         949       6019561   b   W95 FAT32
/dev/hda2           950       4864      32250487*  f   W95 Ext'd (LBA)
/dev/hda5           950       1375       4225063*  b   W95 FAT32
/dev/hda6          1376       1398        104394   83   Linux
/dev/hda7          1399       2633       10402301   83   Linux
/dev/hda8          2634       2824       1052226   83   Linux
/dev/hda9          2825       2995       1052226   83   Linux
/dev/hda10         2996       3086       1052226   83   Linux
/dev/hda11         3087       3217       1052226   82   Linux swap
/dev/hda12         3218       3249        257008*   83   Linux
/dev/hda13         3250       3335        690763*   7   HPFS/NTFS
/dev/hda14         3336       4864      12281681   b   W95 FAT32

[root@test3 ~]# mount /dev/hda5 /mnt/C
mount: /dev/hda5 already mounted or /mnt/C busy
mount: according to stab, /dev/hda5 is already mounted on /mnt/C
[root@test3 ~]#
```

The contents of partition identified as *hda5* will be available under */mnt/C* after execution of the mount command. Once a directory is used to mount, it cannot be used as mount point of another partition.

```
root@test3:~ - Shell - Konsole
Session Edit View Bookmarks Settings Help

[root@test3 ~]# passwd
Changing password for user root.
New UNIX password:
Retype new UNIX password:
passwd: all authentication tokens updated successfully.
[root@test3 ~]#
```

Changing passwords in command prompt.