

This will open the Gadget content directory where you can browse through the available content categories or search for specific types of content.

Once you find the required gadget, click Add to add it to GD. In our example, we've added the Weather Globe, which shows you the current weather as well as the forecast. Once added to the sidebar, click on the down arrow key at the top right corner of the Gadget to access the configuration options and set the location for which you want the weather information. Finally, click on the "Undock from Sidebar" option to allow it to "float" over your Desktop.

Any hidden gadget can be brought to the front by pressing the [Shift] key twice, or by using the Gadgets taskbar button.

This button can also be used to add Gadgets or remove the button entirely from the taskbar. You re-enable it on the taskbar by going to GD's **Preferences > Display** page.

Some Gadgets also support "sending to a friend" via e-mail or Google Talk. For example, if you see an interesting item in the Web Clip or News gadget, right-click on the item, select the "Send To" option and choose your Google Talk friend, or choose to e-mail them using your default e-mail client.

7.10.10 Pause, Prevent or Delete Indexing

If at all you ever wish to pause indexing or re-index the contents of your computer, you can do this by right-clicking on the GD icon in the system tray, clicking the "Indexing" option and selecting "Pause Indexing" or "Re-indexing" options. You can also click on the "Index Status..." option to open the Index Status Web page, which will give you a summary of the current index status of the various file types.

You can also permanently prevent specific files and folders from being indexed. To do this, right-click on the Google Desktop icon in the system tray and select Preferences. This will open the

Preferences > Local Indexing page in your default browser. Scroll down to the section "Don't Search These Items" and click on the "Add file or folder to exclude" link to add the files and folders to be excluded from indexing.

By default, Google retains the index entries for files or folders even if they are deleted. You can check the "Remove Deleted Items" checkbox to remove it from the index. Also, if your files and folders are already indexed, you will need to individually remove the unwanted entries. To do this, search for the data you want removed from Google Desktop, click on the "Remove from Index" link at the top right, select each entry that is to be removed individually, or click on "Select All" at the upper right side to remove all entries.

This removal from the index is permanent unless the entire computer is re-indexed and the removed items are not present in the index exclusion list defined via the **Preferences > Local Indexing** options page. Note that e-mail messages removed from the index will not reappear *unless* they are re-opened and read again. In this case, you would need to manually remove them again using the procedure described above.